



# VPN Tracker 365

## **VPN Tracker 365 Manual**

© 2016 equinux AG and equinux USA, Inc. All rights reserved.

Under copyright law, this manual may not be copied, in whole or in part, without the written consent of equinux AG or equinux USA, Inc. Your rights to the software are governed by the accompanying software license agreement.

The equinux logo is a trademark of equinux AG and equinux USA, Inc., registered in the U.S. and other countries. Other product and company names mentioned herein may be trademarks and/or registered trademarks of their respective companies.

equinux shall have absolutely no liability for any direct or indirect, special or other consequential damages in connection with the use of this document or any change to the router in general, including without limitation, any lost profits, business, or data, even if equinux has been advised of the possibility of such damages.

Every effort has been made to ensure that the information in this manual is accurate. equinux is not responsible for printing or clerical errors.

Revised April 28, 2016

Created using Apple Pages.

[www.equinux.com](http://www.equinux.com)

# Contents

<b>Introducing VPN Tracker 365 .....</b>	<b>5</b>
<b>VPN Tracker Plans.....</b>	<b>7</b>
<b>Getting Started .....</b>	<b>9</b>
Installing VPN Tracker .....	9
Your VPN Tracker 365 account .....	9
<b>Migrating from Previous Versions .....</b>	<b>11</b>
<b>Getting Connected .....</b>	<b>12</b>
<b>VPN Crash Course .....</b>	<b>12</b>
<b>The Big Picture .....</b>	<b>14</b>
<b>Setup for an Existing VPN .....</b>	<b>18</b>
<b>Setup without Configuration Guide.....</b>	<b>20</b>
<b>Importing Connections .....</b>	<b>23</b>
<b>Connecting to Your New VPN .....</b>	<b>24</b>
<b>Working with VPN Tracker.....</b>	<b>25</b>
<b>VPN Shortcuts: Your VPN Cockpit .....</b>	<b>25</b>
<b>VPN Productivity .....</b>	<b>30</b>
Managing Connections and VPN Shortcuts Collections .....	30
VPN Connection Stats .....	31
Menu Bar Item .....	31
Notifications .....	31
Actions .....	32

<b>Notes .....</b>	<b>33</b>
<b>Network Scanner .....</b>	<b>34</b>
<b>Accounting .....</b>	<b>39</b>
<b>Exporting Connections .....</b>	<b>41</b>
<b>Troubleshooting .....</b>	<b>45</b>
<b>Managing VPN Tracker Plans.....</b>	<b>51</b>
<b>Reference .....</b>	<b>60</b>
<b>Settings Reference.....</b>	<b>60</b>
Basic Tab .....	60
Advanced Tab .....	68
Actions Tab .....	77
Export Tab .....	77
VPN Tracker Preferences .....	77
<b>VPN Shortcuts Reference.....</b>	<b>81</b>
<b>Accessing Files &amp; Printers over VPN.....</b>	<b>88</b>
<b>L2TP / PPTP Connections .....</b>	<b>91</b>
<b>VPN and Network Address Translation (NAT) .....</b>	<b>92</b>
<b>Certificates and Smart Cards.....</b>	<b>96</b>
<b>Choosing the Right VPN Device .....</b>	<b>104</b>
<b>Further Resources .....</b>	<b>106</b>
<b>Keyboard Shortcuts.....</b>	<b>107</b>

# VPN Tracker at a Glance

## Search

If you're a consultant with lots of customers, you'll appreciate being able to filter your connection list to find *that* VPN.

## VPN Shortcuts

Everything you need to work over VPN in one place: Applications, servers, websites and more.

## On/Off Switch

Connect and disconnect your VPN by sliding its switch on or off.

## Network Traffic

See what's happening on your VPN connection.

## Add Items

Add a new VPN connection, group or VPN Shortcut

## Toggle Details

Display or hide your connection details or the traffic graph.

## SecureDrop

Share files securely with co-workers using Secure Drop.

## Network Scanner

Explore the remote network and instantly connect to services.

## Accounting

Keep track of your connection time.

## Log

Get troubleshooting advice and see what VPN Tracker is doing.

## Configuration

Set up your VPN or change settings.

## Status

Your VPN at a glance – see your assigned IP address, the remote network address, contact information and notes.

## Contacts & Notes

Jot down notes and store the admin contact for the VPN or the reference number for a client.

## Technical Support

No matter where you are, technical support is just one click away!

The screenshot shows the 'Home Office' VPN Tracker application. The interface is divided into several sections:

- Top Bar:** Includes a 'Log' button, a 'Configure' button, and tabs for 'Status', 'SecureDrop', 'Scanner', and 'Accounting'.
- Left Sidebar:** Contains a search bar, 'VPN Shortcuts', 'Offices' (with 'San Francisco' and 'London Office' listed), and 'Home' (with 'Home Office' listed). Each item has a toggle switch.
- Main Content Area:** Displays a network diagram showing 'This Mac' (192.168.213.192) connected to the 'Internet' (cloud), then to a 'VPN Gateway' (DELL SonicWALL TZ 210, vpntest.equinux.net, 194.145.236.73), and finally to a 'Remote Network' (192.168.213.0/24). Below the diagram, there is a 'Traffic' tab showing 'In' and 'Out' traffic statistics (Current: 0 Byte/s, Total: 744 Byte, Peak: 744 Byte/s) and a line graph. To the right of the graph, there is a section for 'Organization' (equinux AG, equinux sales team), 'Contact' (equinux sales team), 'Email', 'Phone', and 'Website' (http://www.vpntracker.com/us/support.html). Below this, it says 'Last connected: September 24, 2015 at 4:19 PM for 2:18 minutes.' and a 'Technical Support Report (TSR)...' button.
- Bottom Right:** A section for 'Contacts & Notes' with a text area for notes and a 'Technical Support Report (TSR)...' button.



# Introducing VPN Tracker 365

Welcome to VPN Tracker, the leading VPN client on Mac. Whether you are new to VPN or a seasoned VPN guru, this manual will help you get started with VPN Tracker.

## New to VPN Tracker?

- ▶ Install VPN Tracker and start your free demo in → *Getting Started*
- ▶ Take our → *VPN Crash Course* and then → *Get Connected*
- ▶ Find out how using your VPN is a breeze with → *Secure Desktop*

## Upgrading to VPN Tracker 365?

- ▶ See how to → *Upgrade Your License* and how VPN Tracker automatically takes care of → *Migrating from Previous Versions*
- ▶ Explore → *What's New* in VPN Tracker 365

## System Administrators and IT Departments

- ▶ Connect to your existing VPN or set up a VPN from scratch in → *Getting Connected*
- ▶ Set up VPN Tracker for others in → *Exporting Connections*
- ▶ Use the → *Settings Reference* for in-depth configuration information

### VPN Tracker Deployment Guide

- ▶ Are you deploying VPN Tracker to end users in your organization?
- ▶ Are you a consultant setting up VPN Tracker for your clients?
- ▶ Are you managing the VPN Tracker licenses in your organization?

Get the VPN Tracker Deployment Guide for up-to date information and best practices. Download your free copy today at <http://www.vpn-tracker.com>

## Conventions Used in This Document

### Links to External Websites

Sometimes you will be able to find more information on external websites. Clicking links to websites will open the website in your web browser:

<http://equinux.com>

### Links to Other Parts of this Manual

A → *Link* will take you to another place in the manual. Simply click it if you are reading this manual on your computer.

### Tips and Tricks



This manual contains lots of great tips. You can easily spot them by looking for the light bulb icon.

### Advice for Setting up Your VPN Gateway



If you are setting up not just VPN Tracker, but also a VPN gateway, this icon points out recommended settings and things you need to pay attention to when setting up a VPN gateway.

### Warnings



This exclamation mark warns you when there is a setting or action where you need to take particular care.

## Getting Help

VPN Tracker makes VPN simple. However, computer networking and VPNs can be complex and tricky at times, so we have also built in tools

and helpful features that will assist you if you ever run into problems.  
Check out → *Troubleshooting* for more information.

# VPN Tracker Plans

We offer three different VPN Tracker plans to fit your requirements. Find out which plan is right for you.

## VPN Tracker

VPN Tracker is designed for individual users and for end users in corporate environments. It's perfect for getting connected to an office or home network.

## VPN Tracker Pro

VPN Tracker Pro adds advanced features for consultants, network admins and power users.

## VPN Tracker VIP

VPN Tracker VIP includes all features from Pro, plus Remote Connection Wipe, more powerful team management tools, early beta access and additional support.



Regardless of the plan you have purchased, you can always download and use the same copy of the VPN Tracker application. Your license will automatically unlock all the features included in your plan.

## VPN Tracker Plans Compared

	VPN Tracker	VPN Tracker Pro	VPN Tracker VIP
<b>Connectivity</b>			
Connect to one VPN	✓	✓	✓
Connect to multiple VPNs at the same time	–	✓	✓
Connect two sites (Network to Network)	–	✓	✓
Integration of OS X PPTP/L2TP VPN	–	✓	✓
<b>Export</b>			
Export	–	✓	✓
<b>Organization</b>			
Organize your connections in groups	–	✓	✓
Use a condensed layout	–	✓	✓
Search for connections	–	✓	✓
Accounting	–	✓	✓
<b>Tools</b>			
Ping Tool	✓	✓	✓
DNS Lookup Tool	✓	✓	✓
Network Scanner	–	✓	✓
Tools for License distribution and accounting			✓
Remote Connection Wipe			✓
Dedicated Support team			✓
Pre-Release access			✓

	VPN Tracker	VPN Tracker Pro	VPN Tracker VIP
Account Representative			✓

# Getting Started

This chapter shows you how to install VPN Tracker, and how to activate your plan. If you do not have a plan yet, don't worry – we'll also show you how to get a demo plan to try VPN Tracker for free.

## Installing VPN Tracker

You can always download the latest version of VPN Tracker from the VPN Tracker website:

<http://vpntracker.com/download>

There is one single download for all different plans of VPN Tracker.

Once your download has finished, double click the downloaded file “VPN\_Tracker\_365\_9.x.x.zip” if it doesn't open automatically. Then double-click the VPN Tracker 365 app and follow the steps to install VPN Tracker's engine.



## Opening VPN Tracker

Go to your Applications folder in Finder and double-click VPN Tracker 365 to open it.

## Your VPN Tracker 365 account

Accessing your VPN Tracker 365 account is quick and easy. You can start using your plan in a few seconds over any Internet connection.

## How many plans do I need?

VPN Tracker is licensed per-user, so each user that wants to use VPN Tracker needs his own plan. You can use your plan on all of your personal Macs. Plans can be bought in the equinux Online Store.

<https://vpntracker.com>

## Testing VPN Tracker

If you want to make sure VPN Tracker works with your connection and meets your expectations before purchasing, you can request a free demo plan. This will give you access to all VPN Tracker Pro features (except exporting connections). Simply click the button to obtain a demo license when you first open VPN Tracker.



If you set up your VPN connection during your free demo period, VPN Tracker will keep all your settings and details once you activate a purchased license.

Once you're satisfied VPN Tracker suits your needs, you can purchase a full plan right from within VPN Tracker.

### To purchase a license:

- ▶ Click your account name in the upper left corner of the application window

- Click "Choose your plan"
- Select the plan you want to purchase and follow the instructions. Your plan will be activated immediately.

If you prefer, you can also purchase VPN Tracker using your web browser:

<http://www.equinux.com/goto/vpntracker365/buy>

# Migrating from Previous Versions

No matter which version you are coming from, it's easy to migrate all your settings to VPN Tracker 365 to continue working without interruption.



If you are evaluating VPN Tracker 365, don't worry – **your existing connections and settings in previous versions of VPN Tracker remain untouched.**

## VPN Tracker 5, 6, 7 and 8


Your existing connections and settings from the most recent predecessor are automatically migrated to VPN Tracker 365 when you open it for the first time.

If you ever want to migrate your connections again, you can tell VPN Tracker to repeat the migration to ensure you have the latest connections and settings from your old VPN Tracker version: “File > Migrate from VPN Tracker 5/6/7”. Please note that this migration will replace all connections in VPN Tracker 365.

## VPN Tracker 4 (and 3)

You can migrate connections from these versions of VPN Tracker from the File menu (File > Migrate...).

You will find your migrated connections in their own connection group named “VPN Tracker 4” (or “VPN Tracker 3”) in VPN Tracker.




# Getting Connected

## VPN Crash Course

Is this your first time working with a VPN? Read this chapter to get you up to speed.

### VP...What?

VPN Tracker allows your Mac to securely connect to another network over the Internet. Even if your office is located in San Francisco and you're on a business trip in New York, you can work with your applications and files, as if you were in your office.



### How does it work?

As the name implies, VPN Tracker uses VPN (Virtual Private Network) technology to create a connection between your Mac and your remote network. And unlike normal Internet connections, a VPN Tracker connection is encrypted. Think of a VPN as a highly-secure tunnel through the Internet, your very own "secure line" to your office.

In order to use a VPN, you'll need your Mac running VPN Tracker on your end of the connection. On the other end of the connection (the re-

mote side), you need a VPN gateway that accepts your incoming VPN connection.

Once you have set up your connection in VPN Tracker and on the device at your remote location, you are ready to connect and start working remotely using your normal tools and applications.

### What do I need?

To create a VPN connection from your Mac, you need three things:

- ▶ VPN Tracker
- ▶ An Internet connection
- ▶ A VPN gateway

If you're reading this, you probably already have VPN Tracker and an Internet connection for your Mac. So what about a VPN gateway?

### VPN Gateway

A VPN gateway is a hardware device (or in some cases specialized software running on a regular computer) that accepts incoming VPN connections, creating a secure tunnel between its local network and your Mac. In most cases, a VPN firewall or a router with built-in VPN capabilities will act as the VPN gateway.



If there are existing VPN users in your organization you probably already have a properly configured VPN gateway. If not, don't worry – check out the chapter on → *Choosing the Right VPN Device* for some tips on what to look for when buying a VPN gateway.

### What kind of VPN connections does VPN Tracker support?

VPN Tracker supports industry standard IPsec VPN connections. IPsec VPN is fast, secure, and supported by a great variety of devices.




In addition, VPN Tracker Pro also integrates OS X L2TP VPN connections, as well as legacy PPTP connections. For more information, please refer to chapter → *L2TP / PPTP Connections*.

# The Big Picture


To give you a better idea how to set up your VPN, here's a quick overview. We'll look at the details in the following chapters, so don't worry about missing pieces right now – there will be a lot more specific information later on.

## Add a New Connection

- ▶ Click the button in the lower left hand corner of the VPN Tracker window



You will see a list of device profiles. We have device profiles for all the VPN gateways that VPN Tracker has been tested with.



- ▶ Select your VPN gateway from the list. If your VPN gateway is not listed, check the box “Use custom device profile”.
- ▶ Click “Create” to add the new connection

☒ Use custom device profile


Select this option if your device is not in the list, or if you would like to modify expert settings.

## Find Your Configuration Guide

Our engineers have tested a large number of VPN gateways with VPN Tracker. For many of these, detailed configuration guides are available. Now is a good time to check whether a device-specific configuration guide is available.

### In VPN Tracker

- ▶ Click “Configuration Guide” on the Basic tab.



You will be taken to the configuration guide for your device, if available.

### On the Web

All configuration guides are also available on our website:

<http://vpntracker.com/interop>



If a configuration guide is available for your device and you do not yet have VPN set up on your VPN gateway, you can go straight to the guide and follow it. Then continue with the chapters → *Secure Desktop* and → *Working with VPN Tracker* for more information on how to use your VPN connection.



VPN Tracker can also use L2TP or PPTP connections created by OS X. For more information, please see→ *L2TP / PPTP*.

---

# Basic Settings

Let's take a closer look at the essential settings that VPN Tracker needs to connect to your VPN gateway. Depending on your device, some settings may not be shown. If you don't know yet what to fill in, we'll cover each setting in detail later in this chapter.

## Connection Icon

Customize the icon by dragging an image onto the default icon, or choose "Edit > Choose Image..." for a new icon.

## Device Profile

Click to change the device profile.

## VPN Gateway

Enter the public IP address or host name of your VPN gateway, e.g. 203.0.113.48 or vpn.example.com

## Authentication

Choose whether to use a pre-shared key, certificates or hybrid mode for authentication. Most VPN gateways use pre-shared keys.

## Identifiers

Select the type and enter the local and remote identifiers.

**Note:** The identifiers need to be entered in reverse, e.g. "local" in VPN Tracker is what is configured as "remote" on your VPN gateway.

## Connection Name

Click to change the name of your connection.

## Configuration Guide

Click to access the device-specific configuration guide.

## Network Configuration

Select manual configuration or one of the automatic configuration options (not available on all devices).

## Extended Authentication

VPN Tracker will prompt you for username and password if your VPN gateway requests Extended Authentication (XAUTH).

## DNS

VPN Tracker can use a DNS server on the remote network over VPN. It is not necessary to configure remote DNS right away, you can always do so later.

## Advanced Settings

You likely won't have to modify any settings on the Advanced tab, unless:

- ▶ your device uses different settings than the factory defaults and/or the settings proposed in the configuration guide, or
- ▶ there is no device profile for your device in VPN Tracker

In both cases, the goal is to have VPN Tracker's settings for Phase 1 and Phase 2 match exactly what is set up on your VPN gateway.




Some VPN gateways use different terms for phase 1 and 2: Phase 1 is sometimes called "IKE", while phase 2 may be called "VPN" or "IPsec". Check out the → *Settings Reference* for more details.

## Actions and Notes

These settings are **not** relevant to VPN connectivity, so we will skip them for now. They are covered in detail in → *Working with VPN Tracker*.

## Completing Setup

When you're done configuring your VPN, click the „Done“ button on the upper right corner to leave edit mode.



It is **not** necessary to leave edit mode to save the connection or to connect to the VPN. If you make changes while the VPN is connected, reconnect the VPN to apply them.

Now that you have a basic idea how to set up a connection in VPN Tracker, you're ready to apply it to your specific situation.

### Are you connecting to a VPN that's already set up?

If you are connecting to an existing VPN (e.g. one that Windows users are already connecting to), all you need to do is gather a few pieces of information about your VPN gateway to configure VPN Tracker. The next chapter → *Setup for an Existing VPN* has all the details.

### Are you setting up both your VPN gateway and VPN Tracker?

Check if your VPN gateway has been tested with VPN Tracker and if there is a configuration guide available (see → *Find Your Configuration Guide*).

- ▶ If a configuration guide is available, follow it.
- ▶ If no configuration guide is available for your device, or if you are working with an untested device, → *Setup without Configuration Guide* will help you get connected.

### Did you receive a VPN Tracker connection from your administrator?

Follow → *Importing Connections* to see how to use the connection in VPN Tracker.

# Setup for an Existing VPN

When connecting to a VPN that's already set up, your goal is to configure VPN Tracker to match the settings on your VPN gateway. In order to do so, you will need information about the VPN gateway's configuration.

## What if my organization does not support Macs?

We often hear from customers in organizations where Macs are not officially supported for VPN access. It may be difficult to get help if the IT help desk isn't set up to support Mac users. We're here to help!

To find out more about your VPN gateway's configuration, your first stop should be your VPN gateway's administrator: Your network administrator, your IT department or your help desk are good places to ask.

If they cannot help, you may be able to obtain the settings from another VPN client that has already been configured, for example on a Windows PC.

## Obtain the Configuration

### You will always need the following information:

- ▶ The public IP address or host name (e.g. "203.0.113.48" or "vpn.example.com") of the VPN gateway you are connecting to
- ▶ The brand of the VPN gateway (e.g. Cisco, SonicWALL, NETGEAR, ...)
- ▶ The pre-shared key<sup>1</sup> or the client certificate

<sup>1</sup> Not required for SonicWALL with "Use Default Key for Simple Client Provisioning" enabled

<sup>2</sup> Some VPN gateways (e.g. Cisco) refer to the local identifier as "group name" or "group ID"

### You may also need one or more of the following:

- ▶ The address of the network you are connecting to through VPN
- ▶ The local identifier<sup>2</sup>
- ▶ The model name of the VPN gateway (e.g. ASA Series, TZ Series, FVS318N, ...)
- ▶ The settings for phase 1 and 2 (encryption algorithms etc.)
- ▶ Your username and password, if Extended Authentication (XAUTH) is used



If you have any questions about specific settings, please refer to the → *Settings Reference* in this manual. For some settings, in particular phase 1 and 2 algorithms, it may be possible to "guess" them – the reference will tell you if and how.

## Cisco IPsec VPN

If you have a Cisco IPsec VPN connection profile (.pcf), you can import it directly into VPN Tracker (File > Import > Cisco VPN Client Connection).

## Configure VPN Tracker

- ▶ Create a new VPN connection if you have not yet done so (see → *Add a New Connection* for additional information).
- ▶ Enter the settings you obtained in the Basic and Advanced tabs.



---

If there is a configuration guide for your VPN gateway (→ *Find Your Configuration Guide*), refer to it for additional advice. Keep in mind that the configuration guide describes a working setup, but not the only working setup. **In most cases, you won't need to make changes to a working setup on the VPN gateway.**

---

## Connecting

When you're done setting up, skip ahead to → *Connecting to Your New VPN* to see how to connect to your new VPN.

# Setup without Configuration Guide

Almost all IPsec VPN gateways can be used with VPN Tracker, even if they have not been tested with VPN Tracker.

## Set up Your VPN Gateway

### Network Setup

If you haven't already done so, set up your VPN gateway so it is connected to the Internet and to the internal network that you want to access using VPN Tracker. Please refer to your VPN gateway's manual for more information on how to do this.



It is a good idea to carefully choose the address of the VPN gateway's LAN network if you plan to access it through VPN. To avoid address conflicts, use a private network that is not used very frequently (e.g. 192.168.142.0/24, or 10.42.23.0/24).

### VPN Setup

Once you have completed the initial setup of your VPN gateway, it is time to configure VPN on the VPN gateway. Go for the simplest possible configuration first. You can always move to a more sophisticated setup later.

If your VPN gateway's manual has instructions for setting up a VPN connection, follow it. Otherwise, please follow these basic settings as closely as possible:

### Authentication

- ▶ Choose **pre-shared key authentication**.
- ▶ For now, use a pre-shared key that is not too complex to avoid typos. But don't forget to change it to a very strong password later!

### Aggressive Mode vs. Main Mode

- ▶ For most devices, you should use **Aggressive Mode** for now.
- ▶ **Main Mode** is considered more secure, but may not work with all devices for clients connecting from dynamic IP addresses. You can try Main Mode once you've got everything else working.

### Identifiers

- ▶ Choose **Fully-Qualified Domain Name (FQDN) identifiers**, if possible.
- ▶ With most devices, you can enter any identifier you want, it doesn't have to be a valid domain name. Good choices would be:
  - Local identifier: `vpngateway.local`
  - Remote identifier: `vpntracker.local`  
(the remote identifier is sometimes called "peer identifier")
- ▶ Some devices use the group name as the remote identifier.

### Proposals (Phase 1 and 2 Settings)

- ▶ **Encryption algorithms**: AES-128 or 3DES
- ▶ **Hash/Authentication algorithms**: SHA-1
- ▶ **Diffie-Hellman (DH) group 2 (1024 bit)**
- ▶ Enable **Perfect Forward Secrecy (PFS)** using **DH group 2 (1024 bit)**

While these are not the most secure settings, they are compatible with a wide variety of devices. Use them as a starting point. Once you've got the VPN working, switch to stronger algorithms if available (e.g. AES-256, SHA-2, DH group 5 or higher).



## Local Endpoint (Network Access / Policy)

- ▶ On most VPN gateways, you will have to configure the network(s) VPN users can access. This setting is often called “**local endpoint**”, or “**policy**”.
- ▶ Enter the address of the network you would like to access. Usually this will be the same as the VPN gateway’s LAN network (e.g. 192.168.142.0/24).
- ▶ This setting will later be configured in VPN Tracker as the Remote Network.

## Remote Endpoint

- ▶ Some VPN gateways will also ask you to configure the “**remote endpoint**” of the VPN. The remote endpoint is the address VPN clients will be using when connected through VPN.
- ▶ Whenever possible, set this to “any address” or “dynamic” (sometimes also referred to as “0.0.0.0/0”).
- ▶ If your VPN gateway requires a single address to be entered, this will mean that only one VPN client can use this VPN connection at a time. It also means that you will have to take the address you configure on the VPN gateway, and enter it in VPN Tracker as the Local Address.

## VPN Gateway IP Address or Hostname


- ▶ Finally, write down your **VPN gateway’s public (WAN) IP address** or host name.
- ▶ If your VPN gateway’s public IP address is dynamic, you might want sign up with a dynamic DNS service so you can always refer to it by host name.



If any other settings are required by your VPN gateway to set up a basic VPN connection, check the → *Settings Reference* in this manual and your VPN gateway’s documentation for more information on what to configure.

## Configure VPN Tracker

Once you have your VPN gateway set up, enter the settings in VPN Tracker. For your connection, use a custom device profile to have access to all settings.



Then enter your settings. Please refer to → *Getting Connected* to see where required settings are located. Also check the → *Setting Reference* if you are unsure about a specific setting.

### A few final notes:

- ▶ The identifiers are swapped in VPN Tracker. What is **local** from the VPN gateway’s perspective, is **remote** from VPN Tracker’s perspective.

tive, and vice versa. You can set the remote identifier to “Don’t verify remote identifier” so you don’t have to deal with it for now.

- If you were able to select the algorithms and Diffie-Hellman (DH) groups suggested earlier, you do not have to modify any setting on the Advanced tab. However, if the suggested settings were not available on your device, make sure to customize the phase 1 and 2 settings on the Advanced tab so they match what is configured on your VPN gateway.

## Connecting

When you’re done setting up, skip ahead to → *Connecting to Your New VPN* to see how to connect to your new VPN.

# Importing Connections


Find out how to import a connection that you have been given by your IT department or VPN administrator.

## Prerequisites


Before importing a connection, make sure VPN Tracker is installed. If you have not yet downloaded or installed VPN Tracker, or if you haven't activated your license yet, please follow → *Getting Started* first.

## Import Your Connection(s)

- ▶ Locate the connection in Finder and double-click it. Or open VPN Tracker and choose “File > Import > VPN Tracker Connection...” from the menu.




- ▶ You will be asked for the import password. If you don't know the import password, please ask the person who gave you the connection.



## Replacing Existing Connections

If you already have the connection you're about to import, you'll be asked whether to replace your existing connection, or if you would prefer to add this connection as a copy:




### Replacing a connection

If your new connection replaces your existing connection, click “Replace”. Your existing connection will be overwritten.

### Adding a copy

If you would prefer to keep your existing connection and import the new copy, click “Add Copy”.

You'll find the imported connection further down in your connection list. It will have the word “copy” appended to its name, e.g. “Office copy”.



## Replacing existing VPN Shortcuts


Connection files can also include VPN Shortcuts. If the included VPN Shortcuts already exists, you will once again be asked whether you would prefer to replace your existing VPN Shortcut or add the new VPN Shortcut as a copy.

# Connecting to Your New VPN

When you're done setting up your VPN, you're ready to connect. To test your VPN, go to a location outside of the network that you want to connect to.


## Connecting

Click the on/off slider to connect the VPN.




If you are using VPN Tracker for the first time with your current Internet connection, it will test your connection. Wait for the test to complete.

If prompted, enter your pre-shared key and Extended Authentication (XAUTH) user name and password.

A dialog box with a light gray background. In the top-left corner is a circular icon with a white key. To its right is the text 'Please enter the pre-shared key for connection "My VPN Connection".'. Below this is a text field labeled 'Pre-shared Key:' containing ten dots. Under the text field are two checkboxes: 'Show pre-shared key' (unchecked) and 'Store in Keychain' (checked). At the bottom are three buttons: a settings gear icon, a 'Cancel' button, and an 'OK' button.

## Connected?

Connecting may take a couple of seconds. If the On/Off button turns blue that's great – you're connected!



Continue with the chapters → *Secure Desktop* and → *Working with VPN Tracker* to find out how to use your VPN connection.

## Problems?

If there is a problem connecting, VPN Tracker will give you helpful advice and troubleshooting tips. To learn more about troubleshooting VPN connections, visit the chapter → *Troubleshooting*

# Working with VPN Tracker

## VPN Shortcuts: Your VPN Cockpit

Connect to file servers, launch the applications you need, and much more. And stop thinking about VPN connections.


### Setting up a VPN Shortcut

Working over a VPN connection used to be a hassle. First you needed to connect to your VPN. Then you went to Finder in order to connect to your file servers, and finally, you could open the applications you need and get to work.

Not any more! VPN Tracker is designed with your workflow in mind: You click to open the application. VPN Tracker does the rest.

### Building your VPN Shortcut with the Assistant

To add items as VPN Shortcut, select it from the top left corner of the VPN Tracker window and then click “Create VPN Shortcuts...”.



VPN Tracker will guide you through selecting applications, file servers and websites for your VPN Shortcuts Collection. Of course you can always modify your VPN Shortcuts Collection later, so don't worry if you don't yet know what to add.



Make sure you have set up your VPN connection first. To learn how to set up your VPN connection, refer to the chapter → *Getting Connected*.


### Adding Applications to Your VPN Shortcuts Collection

The VPN Shortcuts Assistant will suggest a few commonly used applications. If your application is not among them, click “Other Applica-



tion...” to add the application you want to use.

You can also add applications as VPN Shortcuts later, so don't worry about them now if you're not sure.



## Adding File Servers to Your VPN Shortcut

If you would like to access a file server, enter the details in the VPN Shortcuts Assistant.

### To connect to a Mac-based (AFP) file server:

- ▶ Enter “`afp://`” followed by the IP address<sup>1</sup> of the server, e.g. `afp://192.168.144.11`

### To connect to a Windows-based (SMB) server:

- ▶ Enter “`smb://`” followed by the IP address<sup>1</sup> of the server, e.g. `smb://192.168.144.17`



Alternatively, you can connect to file servers in the OS X Finder.

→ *Accessing Files, Printers and Databases* has more details.


For more information about file servers in VPN Shortcuts Collection, take a look at the → *Secure Desktop Reference*

<sup>1</sup> If your connection is set up to use remote DNS, you may also be able to enter a DNS host name, e.g. “`fileserver.example.com`”

### I don't know my file server's IP address. Can't I just browse for my file servers via the Finder Sidebar?

For technical reasons, when using a VPN connection, your servers won't show up in the Finder sidebar. If you don't have your file server's IP address, you can easily find it out next time you're in your office network (or whatever other network you're connecting to through VPN):

- ▶ Open "Tools > DNS Lookup..."
- ▶ Enter your file server's name and click "Lookup"



After a few seconds, VPN Tracker should tell you the file server's IP address. Again, this will only work when you're actually in your remote network, not if you're connected via VPN.

### Adding Websites as VPN Shortcut

If you have intranet websites that you need to access over VPN, you can add those to your list of VPN Shortcuts as well. Just enter your website URLs when prompted by the VPN Shortcuts Assistant.

### Customizing Your VPN Shortcuts

If you would like, you can customize the name and color of your VPN Shortcut. Then click to finish creating your new VPN Shortcuts.

## Working with VPN Shortcuts



### Starting a VPN Shortcuts Session

Click one of the icons in your VPN Shortcuts section to start working with that application, file server or website. VPN Tracker will automatically connect any necessary VPN connections, and then open your application, connect to your file server, website, etc.



To use VPN Shortcuts when your Mac is physically connected to your VPN's remote network (e.g. at the office), teach VPN Tracker to recognize your remote network using → *Direct Link Detection*.

## Ending a VPN Shortcuts Session

Once you're done working over VPN, simply end your session by clicking the large red button at the bottom of the window. VPN Tracker will take care of disconnecting file servers and disconnecting your VPN.


## Multiple VPN Shortcuts


You can have multiple VPN Shortcuts (e.g. for different clients, departments or tasks). To add a new VPN Shortcut, choose File > New VPN Shortcuts from the menu bar on top of your screen.

## Editing Your VPN Shortcuts

You can easily add, modify or remove VPN Shortcuts items.


### To edit your VPN Shortcuts:

- ▶ Select the VPN Shortcuts Collection that you would like to edit.
- ▶ Click the triangle  at the bottom to switch to edit mode
- ▶ A drawer with new items will open. Drag an item to your VPN Shortcuts Collection to add it. Or drag an existing item outside your VPN Shortcuts Collection to remove it.



To modify an item, click it while a VPN Shortcuts Selection is in edit mode. To finish editing, click on a free space on your VPN Shortcuts area or hit the Esc key.

When you are done configuring, click the triangle again to leave the edit mode.




## Customize the Appearance of Your VPN Shortcuts Selection

You can give your VPN Shortcuts Selection a personal touch, by adding your own picture, choosing your own background and changing icons.


### To customize your VPN Shortcuts icon:

VPN Tracker automatically shows a preview of what's on your VPN Shortcuts Selection. If you wish, you can replace that with a custom icon, simply drag the new icon onto the preview in the sidebar.



### To customize the icons of your VPN Shortcuts Collection items:

- ▶ Switch VPN Shortcuts to edit mode by clicking the triangle






- Drag an image onto one of your VPN Shortcuts icons

### To customize your VPN Shortcuts Collection background

- Switch the VPN Shortcuts section to edit mode by clicking the triangle
  - Drag an image to your VPN Shortcuts area
- or
- Right-click or Ctrl-click the VPN Shortcuts area
  - Select a background image or background color
  - Enjoy the view!



Further information about VPN Shortcuts is available in the → *Secure Desktop Reference*.

# VPN Productivity

Find out about other VPN Tracker features that will help you work more productively with your VPN.


## Managing Connections and VPN Shortcuts Collections

At this point, you probably already have your first VPN Tracker connection. You can see your connection in the sidebar on the left-hand side of the VPN Tracker window.

### Adding More Connections or VPN Shortcuts Selections

To create a new connection or VPN Shortcuts, click the '+' icon in the lower left hand corner of the window.

For more information on setting up a new connection, please refer to the → *Getting Connected* chapter.



### Reordering


Drag & drop your connections and VPN Shortcuts Collections in the sidebar to reorder.

### Renaming

To rename a connection or a VPN Shortcuts Collection, right-click (or hold down Ctrl and click) it in the sidebar and select „Rename“ from the menu.

### Icons

To customize the icon for a connection or



a VPN Shortcuts Collection, drag the new image onto the existing icon in the sidebar.

You can also use „Edit > Choose Icon...“ in the menu to change icons.

## Locking Connections


You can lock a connection with a password to prevent it from being modified (VPN > Lock Connection...). To prevent others from modifying connections you export for them, enable locking in the export settings.

## Organizing Connections in Groups PRO


If you have a lot of connections, it will be useful to divide your connections up into groups, e.g. by client, by branch office, by geographical location etc.

To add a new group, click the '+' icon in the lower left hand corner of the window and select 'New Group'.

You can drag & drop connections and VPN Shortcuts Collections between groups to rearrange them.



To rename, delete or control a group of connections, use the gear menu on the right side of the group.






An exported connection knows the group it belongs to, and will recreate it as needed.

## Search **PRO**


If you are looking for a specific connection, use the search box at the top of the sidebar to find it.



## VPN Connection Stats

When connected to your VPN, you can see statistics for your connection in the sidebar. The traffic graph lets you know how much data is currently being sent and received over your VPN connection, the total amounts of data transferred, and the maximum throughput seen in the last measurement period. It also lists the the algorithms that are in use and the current network settings.

Click to toggle between traffic, network or security information



The graph indicates the amount of traffic currently being transferred over the VPN connection


Click to hide or show the traffic statistics

## Menu Bar Item

You can also control VPN Tracker directly from your menu bar, allowing you full control over your VPN connection, without having to leave the application you're working in.

Access your VPN Shortcuts items from the menu bar.


Click to connect/disconnect VPNs. A checkmark indicates a connected VPN.



The stop button disconnects all VPNs and closes file server connections etc. in VPN Shortcuts Collections.


## Notifications

VPN Tracker shows little popup notifications whenever something interesting happens to your VPN.



You may customize these notifications in "VPN Tracker 365 > Preferences...".

## Actions



### Connect this VPN when VPN Tracker is opened

Enable this option to automatically connect to this VPN whenever VPN Tracker is opened.

### Locations

If you use multiple network locations on your Mac (System Preferences > Network), VPN Tracker can automatically connect or disconnect your VPN connection, depending on the current network location.

- ▶ Switch the slider to “On” to automatically connect in this location
- ▶ Switch the slider to “Off” to automatically disconnect in this location

## Wi-Fi Networks

VPN Tracker will automatically connect to your VPN whenever your Mac connects to the wireless networks you have specified.

### Actions After Connecting

VPN Tracker can take care of any tasks that need to be performed after the VPN connects.


For example, if you always need to connect to a file server, enter it here to make sure it's available any time you connect the VPN. Or if you want to open your company's intranet website whenever you connect, enter it here.



Actions can help you to be even more productive with VPN Shortcuts. For example, if you have certain applications on your VPN Shortcuts Collection that require a file server to be connected, add that file server here to ensure that it's always available to your VPN Shortcuts items.

### Actions Before Disconnecting

If there's anything that needs to be taken care of before the VPN is disconnected, add it here. VPN Tracker automatically adds an action to disconnect all file servers that use the VPN.




Actions that can take a long time have a timeout to make sure VPN Tracker does not keep trying forever.




Actions can also be AppleScript or shell scripts.  
There is no limit to what you can do!

## Notes

If you would like to make a few notes – for yourself, or for others that you're setting up this VPN for, the Notes tab is the right place.



- ▶ Notes are included with exported connections
- ▶ When exporting Accounting records, the reference number and organization can be included for use with billing systems
- ▶ All information from the Notes tab is displayed on the Status tab




# Network Scanner **PRO**

The Network Scanner in VPN Tracker Pro lets you explore the remote network of your VPN, assist users and easily locate hosts and services.

## Scanning Networks

To scan a network, your Mac must be connected to the network via VPN.

- ▶ Select the VPN in the sidebar and connect the VPN.
- ▶ Open the Scanner tab.
- ▶ Click the Scan button to scan the network using a selection of the most popular network services.



If you are connected to a VPN where all network traffic is sent through the VPN (Host to Everywhere), VPN Tracker will ask you to specify the network that you would like to scan.

Depending on the size of the network and your Internet connection, the scan may take a while to complete. You can continue working with VPN Tracker while a scan is in progress. You'll see a notification when the scan is complete.




To be able to use the Network Scanner when you're physically at the remote network and no VPN is needed, set up → *Direct Link Detection* for your VPN connection.

## Customizing Network and Services

By default, the Network Scanner scans for a selection of the most popular network services.

- ▶ To select different services, click the gear icon and check or uncheck the services that you would like VPN Tracker to scan.
- ▶ To turn OS detection on or off, use the checkbox at the top of the settings.
- ▶ To check/uncheck all services, hold down the Option key while clicking a checkbox.
- ▶ To restore the default selection of services and networks, click the "Defaults" button at the top of the settings.




### OS Detection

The Network Scanner can detect the type of host (e.g. OS X, Windows, Linux, Network Equipment, Printers) from the services that are available on that host.

OS detection requires certain services to be included in the scan. If you uncheck a service that is required for OS detection, OS detection will be unchecked as well.

At the bottom of the settings, you can change the network that is being scanned. Select one of the remote networks of the VPN, or enter a custom range or IP address. The more addresses a scan includes, the longer it will take.





# Scan Results

## Display Mode

Show results by address (IP address or host name) or by service.

## Filter Results

Type a search term to locate specific hosts or services. Use the popup button to show or hide groups of hosts or services.

## Your Mac

If your Mac was part of the scan, it is marked with a home icon.

## OS Detection Group

If OS detection is enabled, hosts are grouped according to the OS that was detected (the detected OS can change during the scan as more results come in).

## Services / Hosts

The right side of the window displays the services for the selected host ("By Host") or the hosts for the selected service

## Web Previews

A preview is automatically generated for web servers so you can easily recognize different web

## Instant Connect


Click to connect to the service or open the application associated with this service on your

## Go Button

Click to add the service as a VPN Shortcut, copy IP addresses, or jump to all services of this kind or host.

## Settings

Click to select the services to scan or change the IP range that is being scanned.






# Using Scan Results


## Connect to Services

You can connect to a service right from the Network Scanner, or open the app associated with this service on your Mac.



- ▶ Display the scan results "By Address" or "By Service".
- ▶ On the right side, click the "Connect" or "Open" for the service or host that you would like to connect to.

## Add to VPN Shortcuts Collection


- ▶ To add a service as VPN Shortcut, click the  button for the service that you would like to add to a VPN Shortcuts Collection.
- ▶ Choose "Add to VPN Shortcuts" and select the VPN Shortcuts Collection that you want the service to be added to.
- ▶ You can also drag a service to your VPN Shortcuts Collection in the sidebar.

## Customizing Scan Results

### Renaming Hosts

Renaming hosts in the Network Scanner list makes it easy to locate your most important computers and network devices.

- ▶ Display the scan results "By Address".
- ▶ Right click the host you want to rename.



- ▶ Choose "Rename" and enter a name.

### Automatic Hostname Lookup

VPN Tracker can automatically look up the host names for IP addresses in the Network Scanner. All you need is a → *Remote DNS* server for your VPN that can provide host names for the IP addresses that are being scanned (reverse DNS lookup). Make sure the checkbox "Use for reverse lookup of IP addresses in remote networks" (Basic > DNS) is checked.

### Setting a Custom Icon for a Host

- ▶ Display the scan results "By Address".
- ▶ Right click the host you want to change the icon for.
- ▶ Click "Choose Icon..." to set a custom icon for this host.

### Change the OS Detection Group

The Network Scanner can automatically detect the kind of host – whether it's a Mac running OS X, a PC running Windows or Linux, or a printer or network equipment. OS detection uses the services on a host to determine the most likely type of host.

In some cases, OS detection might put a host into a different group than what it actually is. You can change the group if a host is not detected correctly.

- ▶ Display the scan results "By Address".
- ▶ Right click the host whose group you want to change.
- ▶ Select the new group from the "Group" menu.

### Resetting Scan Results


- ▶ Click "Reset Scan Results" in order to clear the results. Customized host names, icons, and groups will not be modified – if the host is encountered again in a future scan, the customization will be applied.
- ▶ Hold down the Option key while clicking "Reset Scan Results" in order to also reset all customization (names, icons, and groups).

## Scanner Preferences

You can configure the Network Scanner's performance and aggressiveness, and enable or disable Web Preview loading in → *Scanner Preferences*.

# Accounting PRO


Accounting tracks the time you were connected to your VPN. It can assist you with billing your clients and documenting your work.



	Rounded	Traffic	In	Out	Comment
Yesterday 5:14 PM	0.75 h	4.42 MB	3.75 MB	0.67 MB	Set up
3:57 PM	0.25 h	1.41 kB	0.73 kB	0.68 kB	
3:23 PM	0.25 h	1.41 kB	0.73 kB	0.68 kB	
3:15 PM	0.25 h	1.41 kB	0.73 kB	0.68 kB	
2:43 PM	0.50 h	0.78 MB	0.65 MB	0.13 MB	
2:24 PM	0.25 h	1.41 kB	0.73 kB	0.68 kB	
2:23 PM	0.25 h	1.41 kB	0.73 kB	0.68 kB	
2:13 PM	0.25 h	1.41 kB	0.73 kB	0.68 kB	
1:25 PM	0.25 h	135.64 MB	104.07 MB	31.57 MB	
10:58 AM	1.50 h	198.85 MB	196.41 MB	2.44 MB	Assisted Ben with email setup
10:57 AM	0.25 h	222.92 MB	216.56 MB	6.36 MB	Updates

## Customize the Display

- ▶ To select the month for which data is being displayed, click the back/forward buttons next to the month.
- ▶ To select the columns displayed in the Accounting table, right-click the table header and check or uncheck the columns.



	Rounded	Traffic	In	Out	Comment
4.42 MB					
1.41 kB					
1.41 kB					
1.41 kB					
0.78 MB					
1.41 kB					
1.41 kB					



## Add Comments

You can add a comment for every connection to your client's VPN. This helps you to keep track why you used the connection on this day and also makes billing easier. To add a comment, double-click the "Comment" field.

	Rounded	Traffic	In	Out	Comment
Yesterday 5:14 PM	0.75 h	4.42 MB	3.75 MB	0.67 MB	Set up
3:57 PM	0.25 h	1.41 kB	0.73 kB	0.68 kB	

## Exporting Accounting Data

VPN Tracker Pro not just tracks connection time for you, it also lets you export it for Numbers or Excel, or to third-party time tracking or billing systems that can import CSV files.



Export As: Accounting Data - San Francisco

Tags:

Where: Documents

Connection: San Francisco

Export range: This Month (October)

From: 10/ 1/2015 To: 10/31/2015

☒ Date  
☒ Weekday  
☒ Duration  
☒ Duration (quarter hours)  
☒ Local IP  
☒ VPN Gateway IP  
☒ In  
☒ Out  
☒ Comment  
☒ Organization  
☒ Reference number  
☒ Connection Name

Cancel Export

▶ Click "Export" in the "Accounting" tab

▶ Choose "Export for Numbers..." or "Export for Excel..." depending on with which application you want to use the data with

▶ To export data in a customizable CSV format, choose "Custom Export..."

The export can include data for one or more connections, simply select additional connections from the "Connection" popup.

### Reference Number and Organization

To integrate VPN Tracker's accounting with your own time tracking or billing system, an organization and a reference number can be set for each of your VPN connections in the → *Notes* tab

# Exporting Connections PRO


Whether you're quickly exporting a VPN connection for a co-worker, or rolling out VPN Tracker to hundreds of users, VPN Tracker's sophisticated export and convenient installer is there to help.

## Exporting a Connection

Once you have set up and tested a VPN connection, you can export your connection for other VPN Tracker users.

### To export a connection

- ▶ Select the connection
- ▶ Choose „Export...“ from the File menu



- ▶ If you are exporting for users of previous versions of VPN Tracker select the appropriate file format. Not all features are available in previous versions of VPN Tracker. When exporting for earlier versions of VPN Tracker, we recommend testing the exported connection before rolling it out to end users.
- ▶ Set an encryption password for the file. Users of this connection will be required to enter the password once when importing the connection

A screenshot of the 'Export Connection' dialog box in VPN Tracker. It contains the following fields and options: 'Export As:' with a dropdown menu showing 'Test Connection'; 'Tags:' with an empty text field; 'Where:' with a dropdown menu showing 'Documents'; 'Export File Format' with a dropdown menu showing 'VPN Tracker 365'; 'Import Password' section with a note 'Exported connections are encrypted. The password will be required to import this connection.' and two password input fields labeled 'Import password:' and 'Confirm import password:'. At the bottom right are 'Cancel' and 'Export' buttons.

To export multiple connections in a single file, select the connections you would like to export (hold down the ⌘ key to select more than one), and choose File > Export....

## Exporting a VPN Shortcuts Collection

You can also export VPN Shortcuts Collections for your users, along with their connections. Simply select it along with the connections when exporting (hold down the ⌘ key to select more than one item in the sidebar).


To always export a VPN Shortcuts Collection with a connection, check the box for this VPN Shortcuts in the connection's export settings.

A screenshot of the 'VPN Shortcuts' settings section within the export dialog. It features a label 'VPN Shortcuts' followed by two checkboxes: 'Marketing' (checked with a blue square) and 'Tech Ops' (unchecked with an empty square).

## Locking Exported Connections

VPN Tracker offers several ways of locking down and protecting your connection information when you export or deploy connections. To change the security settings for an exported connection:

- ▶ Select a connection
- ▶ Click the Configure... button
- ▶ Click „Export Settings...” at the bottom of the window



Now you can password-protect the connection and adjust which information is visible to the user. All security settings are explained in more detail in → *Export Settings Explained*.

## Export Settings Explained

A screenshot of the 'Pre-Shared Key' and 'Extended Authentication (XAUTH)' settings section. Under 'Pre-Shared Key', there are two checked checkboxes: 'Include pre-shared key from keychain' (with a note 'The included pre-shared key will be added to the user's keychain.') and 'Permit pre-shared keys to be stored in and loaded from the keychain'. Under 'Extended Authentication (XAUTH)', there is an unchecked checkbox 'Include XAUTH login and password' with a dropdown menu set to 'from keychain', and a checked checkbox 'Permit XAUTH credentials to be stored in and loaded from the keychain'.

### Pre-Shared Key

#### Include pre-shared key from keychain

If you have saved the pre-shared key in your keychain, VPN Tracker can include this pre-shared key with the exported connection.

#### Permit pre-shared keys to be stored in and loaded from the keychain

Checking this option will (a) move an included pre-shared key into the user's keychain when importing the connection, and (b) permit users to store their pre-shared key in keychain if none is included with the exported connection.



**The OS X keychain is a very secure way of storing passwords.** However, users will be able to see the pre-shared key via the Keychain Access application.

If you include a pre-shared key but don't permit storing the pre-shared key in keychain, the pre-shared key will be left in the connection. **This is less secure in terms of encryption, but will prevent a user from seeing the pre-shared key.**

### Extended Authentication (XAUTH)

#### Include XAUTH login and password

If you are using Extended Authentication (XAUTH), you can also include a user's XAUTH credentials (username and password) in the ex-

ported connection. Select whether you would like to include the username and password stored in your keychain, or be asked for an XAUTH username and password when exporting the connection.

### Permit XAUTH credentials to be stored in and loaded from the keychain

Checking this option will (a) move included XAUTH credentials into the user's keychain when importing the connection, and (b) permit users to store their XAUTH password in keychain if none is included with the exported connection.

## Security

<b>Security</b>	<input checked="" type="checkbox"/> Don't allow settings to be changed
	<input type="checkbox"/> Hide settings and detailed logs
	<input checked="" type="checkbox"/> Temporarily permit editing with unlock password
	Unlock password .....
	Confirm unlock password .....

### Don't allow settings to be changed

This settings prevents users from making accidental or undesirable changes to their VPN connections. The connection is "locked". Users will be able to see the connection settings, but will not be able to modify them.

### Hide settings and detailed logs

Hides the Basic and Advanced tabs, as well as the more detailed log levels. Only basic logging and troubleshooting information is displayed. Technical Support Reports cannot be created unless an unlock password is set.

### Temporarily permit editing with unlock password


With an unlock password, the connection can be unlocked temporarily, for example if an administrator needs to make changes at a user's computer, or to read the contents of Technical Support Reports.



If you do not set an unlock password, there will be no way to ever make any changes to the exported connection or use a Technical Support Report to analyze a technical problem.

## Unlocking a Locked Connection

A locked connection has a padlock icon in the top right corner of the window. Click it to enter the unlock password and access all settings.



Temporarily unlock a locked connection by clicking the padlock in the upper right corner of the window.

<b>VPN Shortcuts</b>	<input checked="" type="checkbox"/> Marketing <input type="checkbox"/> Tech Ops
<b>Actions</b>	<input type="checkbox"/> Include actions
<b>Contact Info</b>	<u>helpdesk@example.com</u> This email address is the default recipient for Technical Support Reports

## VPN Shortcuts

If you have configured a VPN Shortcuts Collection, you can choose to include it with your exported connection.

Use a VPN Shortcuts Collection to provide your users with a familiar environment for everything they need to do over VPN – network shares, websites, databases, and applications.

VPN Shortcuts selected here are always included when exporting this connection. If you'd like to export additional VPN Shortcuts, simply select them together with your connection before exporting.



You can configure → *Direct Link Detection* so your users are able to use VPN Shortcuts even when no VPN is required, e.g. when connected directly to the office network.

## Actions

If you have configured actions to be executed when the connection is connected or disconnected, you can include them as well. Any settings you have configured in your connection's "Actions" tab will be included.

## Contact info

If your VPN users run into any issues, they can email you a Technical Support Report with details about their connection settings, local internet connection and VPN logs. The email address you enter as your contact info will be set as the default recipient of the report.

# Other Day-to-Day Considerations

## Unlock Password

Experience has shown that when exporting a locked connection, you'll want to unlock it at one point or the other – whether it's making a quick change at an end user's Mac, accessing an end user's Technical Support Report, or even importing the (locked) connection onto your own Mac and accidentally replacing the (unlocked) original.

- ▶ If you do not set an unlock password for a locked connection, there is no way to ever change settings.
- ▶ If you do not set an unlock password and hide the settings and logs, there's no way to ever access the setting.

**We therefore strongly recommend always setting an unlock password.**

## Certificates

If your connection uses certificates for authentication, keep in mind that the certificates are not included with the exported connection. You'll need to distribute the certificates as you would normally do.

VPN Tracker will automatically attempt to use the same certificates on the Mac where the connection is imported. If they are not available, the user will be prompted to select new certificates. For additional information, please refer to → *Certificates*.

## Overwriting Existing Connections

If you have made changes to an connection that you already distributed to your users earlier, it's a good idea to re-use the same connection when exporting (don't create a new one).

That way your users will be prompted to replace their existing connection with the updated one, instead of ending up with another copy, and in the end not knowing which connection is the current one.



# Troubleshooting

In most cases, your connection will work fine if you follow the instructions in this manual. However, computer networking and VPN are complex, so sometimes problems do occur. Read this chapter to learn how to resolve them.

## Missing Settings

If you forgot to fill in a setting, VPN Tracker will point it out to you:



The screenshot shows the 'Office' window in VPN Tracker. The 'Connection Name' is 'My VPN Connection'. Below it, 'Connection based on' is 'Cisco ASA 5500 Series' and 'Need help?' is a link to 'Configuration Guide'. The 'VPN Gateway' field contains 'Host Name or IP Address' and is highlighted with a red box. A tooltip points to this field with the text: 'Please enter the host name or public (WAN) IP address of your VPN gateway.' The 'Network Configuration' dropdown is set to 'EasyVPN'.


Simply fill in the missing information, then try connecting again.

## Connection Errors

In case of any other problem, a yellow warning triangle will show up:

Click the yellow warning triangle to be taken to the log. The log will explain exactly what the problem is. Follow the steps listed in the log to resolve the problem.

If you need additional help, you can email the log to your administrator, or send a Technical Support Report to equinux or to your administrator.



The screenshot shows the 'Office' window with the 'Log' tab selected. The log shows a connection attempt on 2014/09/19 at 18:13:31 that failed. The status is 'Not Connected'. The log entries are: 'VPN Connection Requested', 'Preparing Connection', 'VPN Gateway Unreachable', 'About to Disconnect (Error)', 'Disconnecting (Error)', and 'Not Connected'. A message states: 'The VPN gateway cannot be contacted.' Below this, there are two bullet points: 'Make sure that you have a working Internet connection' and 'Check the host name you entered to make sure it is not mistyped'. A note says: 'If you entered your VPN gateway as a host name (e.g. vpn.example.com) instead of an IP address (e.g. 10.23.42.1):'. At the bottom, there is a 'Log Level' dropdown set to 'Simple', and buttons for 'Email log...' and 'Technical Support Report (TSR)...'.



A Technical Support Report contains the settings and logs necessary for resolving technical problems. Confidential information (e.g. passwords, private keys for certificates) is **not** included in a Technical Support Report. If you contact equinux technical support, always include a Technical Support Report.



Press Cmd-L to open the log in a new window. That way, you can have the log side-by-side with your VPN configuration while making changes to troubleshoot a problem.

## No Access to the Remote Network

If you find yourself in a situation where your VPN appears to be connected, but you cannot access resources (servers, email, etc.) in the remote network, check the following points to resolve the problem.



## Connect to an IP address (instead of a host name)

If you are using a host name (e.g. `fileserver.example.com`) to connect to the resource, please try using its IP address instead.

If the connection works when using the IP address, but not when using a host name, please make sure that your Mac's DNS server is able to resolve this host name to an IP address, or set up a suitable remote DNS server in VPN Tracker. See → *Troubleshooting Remote DNS* for more information.

### Browsing the Network – Bonjour and VPN


Bonjour is the technology that makes your file servers appear in your Finder's sidebar. It depends on broadcasts on the local network. These broadcasts do not travel over VPN. If you are connecting to servers over VPN, you will therefore need to use their IP address (or DNS host name, if using remote DNS).

To learn more about how to connect to servers over VPN, see → *Secure Desktop* and → *Accessing Files, Printers and Databases*

## Check that the IP address you are connecting to is part of the VPN's remote network

Check that the IP address you are connecting to is part of the remote network(s) of the VPN. Also double-check the network mask that you have configured for the remote network(s) in VPN Tracker.

If you are using SonicWALL Simple Client Provisioning or Cisco EasyVPN, the remote network(s) are assigned by your VPN gateway. You can see the remote network(s) on the Status tab.



### About Subnet Masks and Routing Prefixes


A network mask determines the size of the network. For IPv4 networks, it can be written in two ways: As a subnet mask (e.g. 255.255.255.0) or as a routing prefix (e.g. /24). For IPv4 it does not make a difference which one is used. If you enter a subnet mask, VPN Tracker will automatically convert it to a routing prefix (CIDR notation).

Lets take a look at the network 192.168.42.0 / 255.255.255.0 (which is the same as 192.168.42.0/24). This network contains all IP addresses that begin with 192.168.42., for example 192.168.42.1 and 192.168.42.99. It does not contain 192.168.43.1 or 10.1.2.3.

## Make sure the host you are trying to reach knows where to send replies

This one is a little more complex to check. Start with checking if your local address is part of the remote network:

- ▶ Connect the VPN
- ▶ Go to the Status tab
- ▶ Compare the IP address listed under “This Mac” (local address) and the networks listed under “Remote Network”. Is the local address part of the remote network(s)?



In this example, the local address 192.168.213.189 is part of the remote network 192.168.213.0/24

### If the local address is part of the remote network(s):

There are exactly three setups where the local IP address may be part of the remote network(s). If your setup is not one of these, you must choose a local address that is **not** part of the remote network(s).

1. When connecting to a SonicWALL using SonicWALL Simple Client Provisioning or DHCP over VPN.
2. When connecting to a Cisco VPN gateway using Cisco EasyVPN.
3. When connecting to a VPN gateway that can act as an ARP proxy for IP addresses assigned through Mode Config, and/or for fixed local addresses.

That third one is a bit tricky to figure out. If you find a reference to ARP Proxy (or Proxy ARP) in the device’s documentation, or if the manual specifically instructs to choose the local address or the Mode Config address pool to be part of the remote network, then it’s ok for the IP address to be part of the remote network.

**In all other cases you must choose an IP address as the local address (or a Mode Config address pool) that is not part of the remote network(s).** If you are using Mode Config, you need to change the Mode Config address pool on the VPN gateway. Otherwise, simply change the local address in VPN Tracker (Basic > Local Address).

### If the local IP is not part of the remote network(s):

Check if your VPN gateway is the default gateway (router) of its network.

If your VPN gateway is not the default gateway of the remote network, you will have to ensure that responses to all IP addresses used by VPN clients are routed to the VPN gateway. You can do so either by adding a general route on the network’s actual default gateway, or by adding individual routes on each host that VPN clients need to communicate with.

## Troubleshooting Remote DNS


If you can access resources on the remote network using their IP addresses, but not their host names, you will need a suitable remote DNS setup.

Prerequisites for remote DNS:

- A DNS server that is able to resolve those IP addresses exists.
- The DNS server can be reached through the VPN.

To illustrate the steps for debugging remote DNS issues, here's an example setup using remote DNS:

- We have a VPN connection to the remote network 192.168.42.0/24.
- In this network, there's a file server *fileserver.example.com*.
- We can reach this file server using its IP address 192.168.42.10.
- We'd like to reach this file server using its host name *fileserver.example.com*.
- This host name cannot be looked up using public DNS servers, but there is an internal DNS server with IP address 192.168.42.2 that is able to resolve hosts in the *example.com* domain, including *fileserver.example.com*.



The screenshot shows the 'DNS' tab in the Network settings for a VPN connection. The 'Use Remote DNS Server' checkbox is checked. Below it, the 'Receive DNS Settings from VPN Gateway' checkbox is unchecked. The 'DNS Servers' field contains '192.168.42.2' with a help icon. The 'Search Domains' field contains 'example.com' with a help icon. The 'Use DNS Server for' dropdown menu is set to 'Search Domains'. At the bottom, the 'Use for reverse lookup of IP addresses in remote networks' checkbox is checked.

<b>DNS</b>	<input checked="" type="checkbox"/> Use Remote DNS Server
	<input type="checkbox"/> Receive DNS Settings from VPN Gateway
DNS Servers	192.168.42.2 ?
Search Domains	example.com ?
Use DNS Server for	Search Domains
	<input checked="" type="checkbox"/> Use for reverse lookup of IP addresses in remote networks ?

For remote DNS settings to take effect, the VPN needs to be reconnected. We should now be able to connect to *fileserver.example.com* using its host name.




If you set a remote DNS server for “All Domains” instead of specific “Search Domains”, make sure it is a working DNS server that can resolve hosts on the Internet. Otherwise, your Mac will seem to be cut off from the Internet when the VPN is connected.

## Steps to Troubleshoot

If connecting using the host name does not work, the first step is to use the DNS Lookup Tool to verify that the host name can be looked up.

- ▶ Connect the VPN
- ▶ Choose Tools > DNS Lookup from the menu bar on top of the screen
- ▶ Enter the host name (here: *fileserv.example.com*) and click “Lookup”



If the DNS Lookup Tool displays the expected result, remote DNS is configured correctly. In that case, the problem is with the actual connectivity, not DNS.

If DNS lookup fails, then the problem is with remote DNS. The next step is to figure out if the problem is with the remote DNS server itself, or with the remote DNS setup.

- ▶ Open a Terminal window (Applications > Utilities > Terminal)
- ▶ Enter: `dig <host name> @<remote DNS server>` and press return.  
In our example: `dig fileserv.example.com @192.168.42.2`

If you see an “Answer Section” with the correct IP address, then both the connectivity to the DNS server, and the DNS server’s response are ok. In that case, the problem lies with the remote DNS setup. Double-check the configuration in VPN Tracker.

```
# dig fileserv.example.com @192.168.42.2
; <>> DiG 9.7.6-P1 <>> fileserv.example.com @192.168.42.2
;; global options: +cmd
;; Got answer:
;; ->HEADER<- opcode: QUERY, status: NOERROR, id: 30106
;; flags: qr rd ra; QUERY: 1, ANSWER: 1, AUTHORITY: 0, ADDITIONAL: 0

;; QUESTION SECTION:
;fileserv.example.com.      IN A

;; ANSWER SECTION:
fileserv.example.com.      3600    IN A    192.168.42.10

;; Query time: 879 msec
```

If you don’t see an “Answer Section” with the correct IP address, then the remote DNS server is not configured to resolve *fileserv.example.com*.

If you get a timeout error, then the remote DNS server is not reachable over the VPN or it is not a properly configured DNS server.



Some DNS servers are configured to talk only to specific hosts or networks. When connected through the VPN, your Mac may not be part of these. Check your DNS server’s settings or ask the DNS server’s administrator to be sure.

### DNS Troubleshooting Advice for Experts

Command-line tools like `nslookup` and `dig` do **not** accurately reflect DNS resolution on modern OS X versions (but can be very helpful in debugging connections to and results from a single DNS server, as we did above).

- To get exactly the DNS results an OS X application would receive, use the DNS Lookup Tool in VPN Tracker (Tools > DNS Lookup)
- The DNS settings (and search domains) assigned by the VPN gateway using Mode Config, Cisco EasyVPN, or SonicWALL Simple Client Provisioning / DHCP over VPN, are displayed in the connection log and in the “Network” section of the → *VPN Connection Stats*.
- To see the Mac’s currently applicable DNS settings, including those set by VPN Tracker for remote DNS use the Terminal command `scutil --dns`.

# Managing VPN Tracker Plans

All VPN Tracker 365 Plans can be managed under <https://my.vpn-tracker.com>. Here you can create a team and assign plans to users. Your older VPN Tracker license can be managed after logging in to <https://my.equinux.com>. Use the same equinux ID to log in to both sites.

After logging in to <https://my.vpntracker.com> using your equinux ID and password you will see the "Account" section.

The screenshot shows the VPN Tracker 365 account page. At the top, there's a navigation bar with 'HOME', 'ACCOUNT' (active), 'TEAM MANAGEMENT', and 'LOGOUT'. Below this, the 'Account' section displays a user profile for 'Josh' with email 'joshmunichoffice@gmail.com'. A badge indicates 'VPN Tracker 365 VIP' valid until March 31, 2017. There are links to 'Edit your equinux ID', 'Store', and 'Contact VIP support'. Below the account section, a table titled 'PURCHASED PLANS' lists the plans assigned to the account.

Count	Plan	Valid Until
3x	VPN Tracker 365	September 1, 2016
1x	VPN Tracker 365 PRO	September 1, 2016
5x	VPN Tracker 365 VIP	March 31, 2017

© 2016 equinux AG - Imprint

In the "Account" tab you see the VPN Tracker 365 plan assigned to you at the moment:




This screenshot shows a partial view of the VPN Tracker 365 account page, focusing on the account details. It includes the navigation bar with 'HOME', 'ACCOUNT' (active), 'TEAM MANAGEMENT', and 'LOGOUT'. The 'Account' section shows the user 'Josh' with email 'joshmunichoffice@gmail.com'. A badge indicates 'VPN Tracker 365 VIP' valid until March 31, 2017. There are links to 'Edit your equinux ID', 'Store', and 'Contact VIP support'.

Your account will automatically receive the best plan that is available to you, provided you haven't already assigned it to another user.

For example: If you have purchased a VPN Tracker 365 Pro plan and a VPN Tracker 365 plan, the Pro plan will automatically be assigned to your account. Instead, you could assign the Pro plan to another user. In this case your account will automatically use the VPN Tracker 365 plan.

In our example you can also assign both plans to other users. In this case you can manage the plans and the team but don't have a VPN Tracker plan yourself.

In the "Account" tab you also see all VPN Tracker 365 plans purchased with your equinix ID:


PURCHASED PLANS		
Use the <a href="#">team management</a> feature to distribute plans to your team members.		
Count	Plan	Valid Until
3x	 VPN Tracker 365	September 1, 2016
1x	 VPN Tracker 365 <b>PRO</b>	September 1, 2016
5x	 VPN Tracker 365 <b>VIP</b>	March 31, 2017

In the list of plans, you'll see the number of plans available and how long they are valid.


## Assigning VPN Tracker 365 Plans to users

If you purchased multiple VPN Tracker 365 plans for your company or team, you can assign each plan to a user so your colleagues can use VPN Tracker 365 on their Macs.

Before assigning a VPN Tracker 365 plan to a user, you need to create a team under <https://my.vpntracker.com>. To do so, open the "Team Management" tab:




Enter a name for your team and click "Create Team":




Afterwards you'll see the number of plans available and a list of team members. As we just created your team, your team will only contain you as a member:






In order to invite a colleague to your team, just enter his name and email address and click "Invite". Afterwards click "Change plan" to select a VPN Tracker 365 plan for the invited user:



In this way you have assigned a VPN Tracker 365 plan to a user even before he accepted your team invitation:



This allows you to set everything up for your team members. After they accepted your invitation, they can immediately start using the assigned VPN Tracker 365 plan.



Every VPN Tracker 365 user needs his own equinix ID. A user that receives a team invitation from you, clicks the invite link and can then either create a new equinix ID or can log in using his existing account.

If a user leaves your team or does not need a VPN Tracker 365 plan any more you can easily revoke the plan for the user. Just click "Revoke" next to the user in the team member list.




A VPN Tracker 365 Plan is assigned to a user and not to a specific device. If your user has two personal Macs, he can use the same VPN Tracker 365 plan on both computers.

## Migrating users from previous versions of VPN Tracker

If you are an existing VPN Tracker user you can easily migrate your existing VPN Tracker users to VPN Tracker 365.


To do so, visit our website <https://my.equinux.com> and log in using your equinux ID and password. You will see here all VPN Tracker users with a VPN Tracker license assigned.

Click "Export licenses (CSV)" to create a file with a list of all users:



Afterwards log in to <https://my.vpntracker.com> and open the "Team Management" tab. Click here "Import from license manager...". In the next window you can select the downloaded CSV file.


After you have chosen the file, click "Send invitations". The system will then send an invitation to all users from the list. Afterwards you can assign each user a VPN Tracker 365 plan.



## Renaming a team

After you created your team, you can also rename it, if necessary. To do so, please click "Settings" in the left sidebar of the "Team Management" tab.

Enter the new team name and click the "Rename" button:




## Creating groups for your team

Especially when you have many users in your team it is often more convenient to combine multiple users to a sub-division. These sub-divisions are called "Groups" in <https://my.vpntracker.com>. In this way you can have a group for all colleagues from marketing or other departments in your company.

When using VPN Tracker 365 VIP plans, you can also lock a connection to certain groups to use the Remote Connection Wipe functionality.


In order to create a group, go to the "Team Management" tab and click "Manage" in the "Group" section.

Click "Create Group..." and enter now a group name:




## Adding users to a group

After you have created your group, select the group by clicking its name. Click "Add members..."



You will see a list of all team members available:



Click the team members you want to add to this group. Afterwards click "Done".

## Using the Remote Connection Wipe function

All VPN Tracker 365 plans offer you the possibility to use VPN connections that are connected to a certain group and can be remotely removed from all team members' computers. This allows you to prevent unauthorized VPN access.


Follow these steps to set up Remote Connection Wipe

1. Set up a connection and lock it to your team or a specific group
2. Export a connection and distribute it to your team
3. Suspend users from a team and remotely delete all locked connections

### Set up a VPN connection that is locked to a certain group

After you have configured your VPN connection you can enable the Remote Connection Wipe functionality for this connection.

1. Select your connection from the left sidebar
2. Click "Configure" and open the "Export Settings..."
3. In the section "Security" tick the option "Remote Connection Wipe"
4. Tick your team or the groups you want to lock the connection to
5. Click "Close" to save your changed



**Security** ☒ Remote Connection Wipe  
Restrict this connection to your team members and enable Remote Connection Wipe

☐ Munich Office  
☐ Munich Office: HR  
☐ Munich Office: Marketing  
☐ Munich Office: Sales  
Last updated Today 11:54:29

☒ Don't allow settings to be changed  
☐ Hide settings and detailed logs  
☐ Temporarily permit editing with unlock password

Unlock password .....  
Confirm unlock password .....

In Addition you can choose to "Hide settings and detailed logs" and to "Temporarily permit editing with unlock password".

### Export your locked connection and share it with your team

Once you have enabled the Remote Wipe Connection functionality for your VPN connection, export your connection and distribute it to your team.

To do so

1. Choose your connection from the left sidebar in the VPN Tracker app
2. Choose "File > Export" from the top menu bar
3. Set an export location and enter an import password for maximum security
4. Click "Export"

Export As:  ▼

Tags:

Where:  ▼

**Export File Format**  ▼

**Import Password**

Exported connections are encrypted. The password will be required to import this connection.

Import password:

Confirm import password:

**Remote Connection Wipe**

This connection can be used by VPN Tracker 365 plan users in the following Teams: Munich Office

In the export window you will also see a short information that this connection is locked to your team or a group. Click "Edit..." for a quick access to the security export settings.



You can now send the exported connection to your team member. All they have to do is to double click the file and to enter the import password if necessary. The connection is then available in VPN Tracker and ready to use.

## Suspend users and remotely delete connections

Everything is now set up so you can suspend and remove users from a group and remotely wipe all locked connections if necessary.

In order to suspend and wipe, please follow these steps:

1. Log in to <https://my.vpntracker.com> using your equinix ID and password.
2. Open the "Team Management" tab.
3. Click "Suspend & Wipe..." You will see a confirmation window.

Team member	Plan	Actions
 Tom Hartfield	<b>VPN Tracker 365 VIP</b> Valid until March 31, 2017	<input type="button" value="Change plan..."/> <input type="button" value="Suspend &amp; Wipe..."/> <input type="button" value="Remove member..."/>
 Josh manager	<b>VPN Tracker 365 VIP</b> Valid until March 31, 2017	The best available plan is automatically selected for you.

4. Click here "Suspend & Wipe Connections".

Suspend & Wipe connections

Do you really want to suspend **Tom Hartfield** ? Note: Any connections the user has that are locked to this team or any of its groups will be wiped from his Macs.

Please note that this will wipe all connection the user has that are locked to his team or any of its groups from his computer.



VPN Tracker 365 Remote Wipe always wipes all the connections given to the affected team member, rather than individual connections. This is by design, as it allows to wipe connections without any information about the specific VPN connection.

## Administrating Payments and Subscriptions


Besides of managing and assigning VPN Tracker 365 plans, you can also administrate subscriptions and payments under <https://my.vpn-tracker.com>

[tracker.com](https://my.vpn-tracker.com). Change subscription renewal settings or download invoices for your purchases.

Open the "Account" tab and click "Payment & Subscription" from the left sidebar:

Here you can enable or disable the auto-renewal for subscriptions and see further details like the credit card that will be used to renew your subscriptions.

Click "Invoices" in the left sidebar to access all the invoices for your equinix ID. Even for non VPN Tracker 365 purchases.



## Further Questions?

You can find the latest news and compatibility information on our support and FAQ website:

<http://equinux.com/support>

## Contacting Technical Support

If you can't resolve your issue with the information available on our website or in this guide and would like to contact Technical Support through our website, please be sure to include the following information:

- ▶ The manufacturer and model and firmware revision of the VPN gateway
- ▶ A Technical Support Report from VPN Tracker (Help > Generate Technical Support Report)
- ▶ Screenshots of what you have configured on your VPN gateway, in particular all VPN-related settings
- ▶ A detailed description of the problem and the troubleshooting steps you have already taken

# Reference

## Settings Reference

This chapter describes the settings available in VPN Tracker. Settings are grouped by location and sorted from top to bottom as they occur in VPN Tracker. Where possible, related settings and the corresponding settings on a VPN gateway (and the terms different vendors use) are also included.

### Basic Tab

The screenshot shows the 'My VPN Connection' settings window with the 'Basic' tab selected. The window has a dark header with a key icon and the title 'My VPN Connection'. Below the header are tabs for 'Basic', 'Advanced', 'SecureDrop', 'Actions', and 'Notes'. The 'Basic' tab contains several sections: 'Connection Name' (My VPN Connection), 'VPN Gateway' (Host Name or IP Address), 'Network Configuration' (Manual Configuration, Host to Network topology, Local Address IP Address, Remote Networks Network Address), 'Authentication' (Pre-shared key, Extended Authentication (XAUTH) Off), 'Identifiers' (Local Fully Qualified Domain Name (FQDN), Remote Fully Qualified Domain Name (FQDN)), and 'DNS' (Use Remote DNS Server checkbox). At the bottom are buttons for 'Manage Team & Plans...', 'Export Settings...', and 'Export...'.

### Connection Name

A name for the connection. You may choose any name you like.

**Availability:** always (use the Edit menu to change the name if locked)

### VPN Gateway

The public IP address or host name of the VPN gateway to connect to.

**Related Settings:** Advanced > IPv6 > Use IPv6 VPN gateway address when available

**Availability:** always

**VPN Gateway Setting:** WAN IP address, public IP address, external IP address

### Network Configuration

VPN Tracker supports a number of vendor-specific and vendor-independent automatic configuration methods.

#### Mode Config

A vendor-independent automatic configuration method that is capable of transmitting the settings for the local address and the remote DNS settings (DNS servers and search domain).

The "active" and "passive" variants are used to resolve interoperability issues with some devices.

**Related Settings:** Basic > Network Configuration > Local Address  
Basic > Remote DNS > Receive DNS Settings from VPN Gateway

**Availability:** Depending on the selected device profile. Use a custom device profile to be able to select any method.



**VPN Gateway Setting:** Mode Config, Config Mode, IKE-CFG

### Cisco EasyVPN

An extension of Mode Config for Cisco devices that is also capable of transmitting the Remote Network(s) and Perfect Forward Secrecy (PFS) setting.

The "passive" variant can be used to resolve problems when the general EasyVPN setting does not work with a particular device.

If you are using EasyVPN with a custom device profile, make sure to turn on "Identify as Cisco Unity Client" on the Advanced tab.

**Related Settings:** Basic > Network Configuration > Local Address  
Basic > Network Configuration > Remote Networks  
Basic > Remote DNS > Receive DNS Settings from VPN Gateway  
Advanced > Interoperability > Cisco

**Availability:** Depending on the selected device profile. Use a custom device profile to be able to select any method.

**VPN Gateway Setting:** No special settings are needed to use Cisco EasyVPN with EasyVPN-capable Cisco devices. For more details, refer to our Cisco configuration guides.

### SonicWALL DHCP over VPN

An automatic configuration method implemented by SonicWALL devices that is capable of transmitting the settings for the Local Address and the Remote DNS settings (DNS servers and search domain).

**Related Settings:** Basic > Network Configuration > Local Address  
Basic > Remote DNS > Receive DNS Settings from VPN Gateway

**Availability:** Depending on the selected device profile. Use a custom device profile to be able to select any method.

**VPN Gateway Setting:** GroupVPN > Client > Virtual Adapter Setting > DHCP Lease (*or* DHCP Lease or Manual Configuration) + suitable configuration for DHCP server and VPN > DHCP over VPN.

### SonicWALL Simple Client Provisioning (SCP)

An automatic configuration method implemented by SonicWALL devices that can supply all settings of a VPN connection to the client.

**Related Settings:** Basic > Remote DNS > Receive DNS Settings from VPN Gateway

**Availability:** Depending on the selected device profile. Use a custom device profile to be able to select any method.

**VPN Gateway Setting:** No special configuration needed. Requires SonicOS 4.0 or newer.

## Topology

In most cases, the topology should be set to **Host to Network**. This means that a single host (= your Mac) connects to one or more remote networks through VPN. Only network traffic destined for these networks is sent through the VPN, all other traffic is sent out unmodified through the Mac's Internet connection.

Other possible topologies are:

### Host to Everywhere

A single host tunneling all its Internet traffic through VPN. This is equivalent to a Host to Network connection with a remote network of 0.0.0.0/0.

For Host to Everywhere to work, the VPN gateway must accept a policy with a 0.0.0.0/0 endpoint, and also take care of the routing and Network Address Translation (NAT) for the VPN client when it tries to access the Internet.

### Network to Network **PRO**

A (local) network being connected to another (remote) network, with the Mac running VPN Tracker acting as the local VPN gateway, and another

er VPN gateway at the remote end. This can be used to connect a branch or home office with multiple computers to a main office. The Mac running VPN Tracker needs to have routing enabled and has to be configured as the router for the other computers that are to use the VPN.

### Host to Host

A single host (= your Mac) accessing another single host (e.g. a single file server, email server etc.) through VPN.

**Related Settings:** Basic > Local Address, Basic > Network Configuration, Basic > Remote Networks

**Availability:** Not available with Cisco EasyVPN and SonicWALL Simple Client Provisioning. Network to Network requires VPN Tracker Pro.

**VPN Gateway Setting:** Set default route as this gateway (SonicWALL), Allow all traffic through tunnel (WatchGuard), or determined implicitly by VPN endpoints.

### Local Address

The local address is the IP address that the Mac running VPN Tracker uses in the remote network when connected through VPN<sup>1</sup>.

If the local address is left empty, the current IP address of the Mac's en0 network interface will be used. Since this is most likely a private IP address, it is not unique worldwide. In order to avoid situations where two clients coming in through VPN using the same IP, **do not leave the local address empty when you have multiple VPN users**. In that case, always set a unique local address for each client.

<sup>1</sup> In IPsec terms: the local endpoint of the IPsec Security Association (SA)

<sup>2</sup> Such VPN gateways typically have you configure a specific IP address for the client to use and/or have a setting called "Proxy ARP" or "Tie remote stations into the LAN"

<sup>3</sup> In IPsec terms: the remote endpoint of the IPsec Security Association (SA)

The local address should be from a private subnet, and must **not** be part of the remote network(s) of the VPN connection (unless the documentation of your VPN gateway specifically instructs you to do so<sup>2</sup>).

**Related Settings:** Basic > Topology, Basic > Network Configuration

**Availability:** Not available when an automatic configuration method is being used. When a Network to Network topology is used, the setting is called "Local Networks" and describes the local network(s) to which the VPN tunnel applies.

**VPN Gateway Setting:** Remote (IP) address, peer (IP) address, remote endpoint, remote network

### Remote Networks

The network(s) the VPN connects to<sup>3</sup>. Traffic destined for these network(s) will be tunneled over the VPN.

The network(s) can be entered in CIDR notation (e.g. 192.168.42.0/24) or – for IPv4 connections – using the subnet mask (e.g. 192.168.42.0/255.255.255.0).

Always make sure you are using a correct network address. VPN Tracker will try to help you with this, so it might change your input to turn it into a correct network address. Please double check the changes that VPN Tracker made, and correct them if necessary.

**Related Settings:** Advanced > Phase 2 > Establish a separate tunnel for each remote network, (Cisco only) Advanced > Interoperability > Cisco > Establish a shared tunnel to 0.0.0.0/0 for split-tunneling

**Availability:** Not available when EasyVPN or SonicWALL Simple Client Provisioning are used. For these setups, the VPN gateway supplies the networks.

When a Host to Host topology is used, the setting is called "Remote Address" and describes the single remote address the VPN tunnel applies to.

**VPN Gateway Setting:** Local (IP) address, local endpoint, local network

## Authentication

The authentication method VPN Tracker uses. Three methods are available:

### Pre-Shared Key

The VPN client is authenticated using a shared password, the pre-shared key. This is the most commonly used authentication method.

It is possible to store the pre-shared key in the OS X keychain, or be prompted every time the VPN connections.

### Certificate

The VPN client and the VPN gateway mutually authenticate using X.509 certificates (RSA signatures). This method is very secure, but requires an infrastructure for creating and distributing certificates, and a VPN gateway that supports it.

The client's certificate and private key (also called an "identity") need to be present in the OS X keychain.

The VPN gateway's certificate can in most cases be sent by the VPN gateway and verified just as a web browser would do for HTTPS, however, it is also possible to add it to the local keychain and select that specific certificate in VPN Tracker.

## Hybrid Mode

The VPN gateway authenticates itself with a certificate, and users authenticate themselves through Extended Authentication (XAUTH). This method is supported by a small number of vendors (e.g. Check Point) and considered more secure than using an Aggressive Mode connection with just a pre-shared key.

The VPN gateway's certificate can in most cases be sent by the VPN gateway, but it is also possible to add it to the local keychain and set that specific certificate in VPN Tracker.

**Related Settings:** (certificates only) Advanced > Certificates (pre-shared key only) Advanced > Phase 1 Diffie-Hellman Group, Advanced > Additional Settings > Credentials

**Availability:** According to the selected device profile.

**VPN Gateway Setting:** (Pre-Shared Key) Pre-shared secret, shared secret, password, key, (Certificates) X.509 certificates, RSA signatures

## Extended Authentication (XAUTH)

Extended authentication is a way of authenticating individual users on top of one of the general authentication methods, pre-shared key or certificates (hybrid mode already incorporates XAUTH).

In its basic form, XAUTH asks for a username and password, however it is also possible for the VPN gateway to ask for passcodes (such as the ones generated by RSA SecurID tokens) etc.

It is possible to store the XAUTH username and password in the OS X keychain, or be prompted every time the VPN connections.



XAUTH can be set to "Automatic", even if it is actually turned off on the VPN gateway. The VPN gateway will tell VPN Tracker if XAUTH should be used or not. However, there are VPN gateways that need XAUTH specifically turned on or off, that's where the "Off" and "Always" settings can help.

**Related Settings:** Advanced > Additional Settings > Credentials

**Availability:** According to the selected device profile.

**VPN Gateway Setting:** XAUTH, user authentication

## Identifiers

The identifiers are small pieces of identifying information that VPN Tracker and the VPN gateway use to recognize each other.

**Related Settings:** Basic > VPN Gateway (for "Remote Endpoint IP Address")

Basic > Authentication > Certificates (for "Local/Remote Certificate")

**Availability:** Identifiers are determined automatically if SonicWALL Simple Client Provisioning is used.

**VPN Gateway Setting:** The local identifier from VPN Tracker's perspective is the remote (!) identifier from the VPN gateway's perspective, and vice versa. Therefore you will normally have to swap the identifiers configured on the VPN gateway when entering them in VPN Tracker:

Local Identifier: Remote Identifier (or client/peer identifier/identity/ID)  
 Remote Local Identifier (or own/my identifier/identity/ID)  
 Identifier:

## Local Identifier

The identifier that VPN Tracker uses to identify itself to the VPN gateway. The VPN gateway uses the identifier to map the incoming connections to the VPNs it has configured.



Make sure that the local identifier type and value in VPN Tracker match what the VPN gateway expects! Otherwise the VPN gateway may refuse or silently drop the connection.

## IP Address

An IP address is used for identification. Make sure to enter the IP address the VPN gateway expects.

## Local Endpoint IP Address

Same as "IP Address", but VPN Tracker will automatically use the Mac's current local IP address as the value. Useful if your VPN gateway permits incoming connections using any IP address-based identifier.

## Fully Qualified Domain Name (FQDN)

A fully qualified domain name (FQDN) is used for identification (e.g. client.example.com).

## Email (User FQDN)

An email address is used for identification (e.g. vpntracker@example.com).



Some VPN gateways expect FQDN or User FQDN type identifiers that are neither valid FQDNs nor email addresses. This is ok. Simply enter whatever your VPN gateway expects you to use (e.g. a connection identifier, user name or group name).

## Key ID

An identifier for vendor-specific use. Cisco EasyVPN devices use this for the group name of the connecting user.

### ASN.1 DN

An ASN.1 Distinguished Name (DN) is used for identification. Normally this is used in conjunction with certificate-based authentication. Enter the (correctly formatted) ASN.1 DN that the VPN gateway expects.

### Local Certificate

The identifier is the ASN.1 Distinguished Name taken from the subject of the local certificate (only possible when using certificates for authentication).

### Remote Identifier

The identifier that VPN Tracker should expect from the VPN gateway. VPN Tracker will compare the actual identifier sent by the VPN gateway to the one configured here. If the identifiers do not match, the connection attempt will be stopped and an error displayed in the log.

### Don't verify remote identifier

Turn off identifier verification (e.g. for testing). Identifier verification provides minor security benefits for Aggressive Mode connections, but should always be used for Main Mode connections.

### IP Address

An IP address is used for identification. Enter the IP address the VPN gateway sends. It is often, but not always, the VPN gateway's public IP address.

### Remote Endpoint IP Address

Same as "IP Address", but VPN Tracker will automatically use the public IP address of the VPN gateway.

### Fully Qualified Domain Name (FQDN)

A fully qualified domain name (FQDN) is used for identification (e.g. vpn.example.com). Enter the FQDN the VPN gateway sends.

### Email (User FQDN)

An email address is used for identification (e.g. vpnservice@example.com). Enter the email address the VPN gateway sends.



Some VPN gateways use FQDN or User FQDN type identifiers that are neither valid FQDNs nor email addresses. This is ok. Simply enter whatever your VPN gateway sends as its identifier.

### Key ID

An identifier for vendor-specific use.

### ASN.1 DN

An ASN.1 Distinguished Name (DN) is used for identification. Normally used in conjunction with certificate-based authentication. Enter the (correctly formatted) ASN.1 DN that the VPN gateway sends.

### Remote Certificate

The identifier is the ASN.1 Distinguished Name taken from the subject of the remote certificate (only possible when using certificates for authentication).

## DNS

### Use Remote DNS Server

VPN Tracker can use a name (DNS) server in the remote network of the VPN to look up certain (or all) host names. This is useful if your organization operates an internal DNS server that can look up host names of computers on the internal network.

**Availability:** always

### Receive DNS Settings from VPN Gateway

When checked, VPN Tracker will use the DNS settings transmitted by the VPN gateway during automatic configuration. To see if your VPN gateway transmits such information, turn off Remote DNS, then connect. VPN Tracker will show a message in the log suggesting to turn on Remote DNS if settings have been transmitted.

**Related Settings:** Basic > Network > Automatic Configuration  
Basic > DNS > Use Remote DNS Server

**Availability:** Available if an automatic configuration method is selected and “Use Remote DNS Server” is turned on.

## DNS Servers

The IP address of a remote DNS server. To enter more than one server, click the plus button to get additional input fields.

**Related Settings:** Basic > DNS > Use Remote DNS Server  
Basic > DNS > Use DNS Server for

**Availability:** Available if “Use Remote DNS Server” is turned on, and “Receive DNS Settings from VPN Gateway” is turned off.

## Search Domains

The search domain(s) to use. To enter more than one search domain, click the plus button to get additional input fields.

If “Use DNS Server for” is set to “Search Domains”, the search domain(s) will also be used to determine the domains the remote DNS server is being used for.

**Related Settings:** Basic > DNS > Use Remote DNS Server  
Basic > DNS > Use DNS Server for

**Availability:** Available if “Use Remote DNS Server” is turned on, and “Receive DNS Settings from VPN Gateway” is turned off.

## Use DNS Server for

This setting determines the scope of the remote DNS server(s). It is possible to use the remote DNS server(s) for all DNS lookups, or just for hosts in a specific domain.

## All Domains

While the VPN is connected, the remote DNS server is used for every DNS lookup on this Mac, not just hosts that are part of the remote network.



When using this option, it is important to make sure the VPN connection and the remote DNS server are correctly configured: If one or both are not working, the Mac will appear to be cut off from the Internet while the VPN is active.

## Search Domains

The remote DNS server is used only for looking up host names that are part of the search domain(s). At least one search domain must be configured.

## Search Domains (if available)

“Receive DNS Settings from VPN gateway” only: If the VPN gateway transmits a search domain, the remote DNS server is used only for looking up host names that are part of the search domain(s). If no search domain is transmitted, the remote DNS server is used for every DNS lookup on this Mac while the VPN is connected.

**Related Settings:** Basic > DNS > Search Domains  
Basic > DNS > Use Receive DNS Settings from VPN Gateway

**Availability:** Available if “Use Remote DNS Server” is turned on.

## Use for reverse lookup of IP addresses in remote networks

The remote DNS server is used for reverse lookups (mapping IP addresses back to host names) in the remote networks. When the remote DNS server is used for “All Domains”, this happens automatically.

**Related Settings:** Basic > Network Configuration > Remote Networks  
Basic > DNS > Use DNS Server for




**Availability:** Available if “Use Remote DNS Server” is turned on.



Need more help configuring your remote DNS setup? A chapter on → *Troubleshooting Remote DNS* is available in this manual.

## Advanced Tab

 My VPN Connection Done

BasicAdvancedSecureDropActionsNotes

Phase 1

Exchange modeAggressive Mode

Lifetime28800 seconds

Encryption algorithm

☐ AES-256

☐ AES-192

☒ AES-128

☒ 3DES

Hash algorithm

☒ SHA1

☒ MD5

☐ SHA-256

Diffie-HellmanGroup 2 (1024 bit)

Phase 2

Lifetime28800 seconds

Encryption algorithm

☐ AES-256

☐ AES-192

☒ AES-128

☒ 3DES

Authentication algorithm

☒ HMAC SHA1

☒ HMAC MD5

☐ HMAC SHA-256

Perfect Forward Secrecy (PFS)DH Group 2 (1024 bit)

Traffic ControlAlways exempt the addresses below from VPN

Address

☐ Force traffic over the VPN if remote networks conflict with local networks

NAT-TraversalAutomatic

Connection timeout30 seconds (retry every 5 seconds, up to 5 times)

Interoperability

General

☒ Send INITIAL-CONTACT message

Important: If you select this option, some devices may disconnect other VPN users.

☒ Advertise as Dead Peer Detection (DPD) capable

☒ Perform active Dead Peer Detection every 20 seconds if necessary

Cisco

☐ Send Cisco Unity Vendor ID

IPv6

☐ Prefer IPv6 VPN gateway address, if available

Additional Settings

☐ Show additional settings

Manage Team & Plans...

Export Settings...

Export...

## Establishing the VPN: Phases, Proposals and Device Profiles

An IPsec VPN connection is established in two phases. In phase 1, VPN Tracker and the VPN gateway verify each other's identity and negotiate encryption keys through which the actual setup of the VPN, phase 2, will be secured.

- ▶ In each phase, VPN Tracker sends the algorithms it is willing to use, as well as a few other settings to the VPN gateway (the "proposals"). The algorithms that VPN Tracker sends are determined by the settings for Phase 1 and 2 on the Advanced tab.
- ▶ The VPN gateway then selects one set of algorithms, or responds with an error (typically something like "no proposal chosen") if it does not agree to use any of the proposed algorithms.

At first glance, it would seem a good idea to simply propose all possible algorithms to the VPN gateway, hoping that it will agree with at least one proposal. However, there are several problems with this approach:

- ▶ Selecting too many algorithms causes data packets on the network to be so large they need to be split up ("fragmented"). Many VPN gateways outright refuse these fragmented VPN packets, and intermediate routers often have difficulties with fragmented VPN data packets as well.
- ▶ Some VPN gateways refuse connection attempts altogether that contain many proposals or algorithms unsupported by the VPN gateway, most likely to serve as an intrusion prevention measure.
- ▶ It is desirable to offer only those algorithms providing a very high level of security.

In the device profiles shipping with VPN Tracker, two or three algorithms that are most commonly used with a given device have been selected.

This increases the chance of a successful connection, even if the exact configuration is not known (while still keeping the data packets small



enough to not be fragmented). However, if you know your VPN gateway's exact configuration, it is best to select exactly one proposal (combination of encryption, authentication/hash algorithm, and DH group) that your VPN gateway is set up to use.

## Phase 1

In phase 1, using the pre-shared key or RSA signatures, VPN Tracker and the VPN gateway negotiate encryption keys with which the set up of the actual VPN tunnel (phase 2) will be secured, and verify each other's identity.

**Related Settings:** Basic > VPN Gateway, Basic > Network Configuration > Automatic Configuration, Basic > Authentication, Basic > Identifiers

**Availability:** Phase 1 settings are not configurable when SonicWALL Simple Client Provisioning is used.

**VPN Gateway Setting:** Phase 1 proposals, phase 1, IKE

## Exchange Mode

The Exchange Mode determines how the initial steps of establishing a VPN connection take place. The setting must match the exchange mode selected on the VPN gateway.

## Aggressive Mode

Aggressive Mode is faster and requires less information, in particular, it does not require the IP address of the connecting client to be known prior to connecting.

## Main Mode

Main Mode is more secure but often requires the IP address of the connecting client to be known beforehand.



Most VPN gateways only support Aggressive Mode connections for VPN clients connecting from dynamic IP addresses or from behind a NAT router.

## Lifetime

For security reasons, the encryption keys of a VPN connection are periodically re-negotiated. The lifetime determines when this takes place. The setting must match the lifetime for phase 1 on the VPN gateway, however a misconfiguration will usually not show up right away, but will only be recognizable when the re-negotiation does not work properly.



If you are setting up your VPN gateway from scratch: It is common to select a lifetime of between 1 and 24 hours (3600 to 86400 seconds).

## Encryption Algorithm

The encryption algorithm to use for phase 1 of the connection. It must match the algorithm configured on the VPN gateway for phase 1.



If you are setting up your VPN gateway from scratch: Each VPN gateway uses different hardware and has a different selection of algorithms available, however, most support at least one of AES-128, 3DES or DES, so if there is no information what your VPN gateway might be using, try those.

AES-256 is considered to be the most secure algorithm. All AES variants and 3DES provide reasonably good security. Use DES only if there's no better choice.



In case you do not know what is configured on your VPN gateway, it is possible to select more than a single algorithm. VPN Tracker will then offer all selected algorithms to the VPN gateway and negotiate which one to use.

To avoid fragmentation of network packets or triggering intrusion prevention mechanisms on VPN gateways, it is not recommended to select more than two or three algorithms

### Hash Algorithm

The hash algorithm used for phase 1 of the connection. It must match the algorithm configured on the VPN gateway for phase 1.



If you are setting up your VPN gateway from scratch: Use SHA-1 if possible. Only use MD5 if no other algorithm is available.

If you own a modern device, it is possible that it already supports SHA-2, which offers additional security.



In case you do not know what is configured on your VPN gateway, it is possible to select both SHA-1 and MD5 here, most VPN gateways will be able to negotiate which one they want to use.

### Diffie-Hellman (DH) Key Exchange

The key length to use for the Diffie-Hellman key exchange. It must match the key length (group) selected on the VPN gateway for phase 1.

If you are getting inexplicable errors about an incorrect pre-shared key, double-check that the Diffie-Hellman group matches the VPN gateway's configuration.



If you are setting up your VPN gateway from scratch: Choose at least "Group 2 (1024 bit)" whenever possible.

Many VPN gateways support up to "Group 5 (1536 bit)", and it is a good idea to use that if it is available. Some recent high-end devices support up to "Group 18 (8192 bit)".

## Phase 2

This second phase of the connection establishes the actual VPN tunnel. All settings here must match the respective setting on the VPN gateway.

**Related Settings:** Basic > Network Configuration

**Availability:** Phase 2 settings are not configurable when SonicWALL Simple Client Provisioning is used.

**VPN Gateway Setting:** Phase 2 proposals, phase 2, IPsec, VPN, tunnel

### Lifetime

For security reasons, the encryption keys of a VPN connection are periodically re-negotiated. The lifetime determines when this takes place. The setting must match the lifetime for phase 2 on the VPN gateway, however a misconfiguration will usually not show up right away, but will only be recognizable when the re-negotiation does not work properly.



If you are setting up your VPN gateway from scratch: The lifetime for phase 2 can be different from the phase 1 lifetime, if it is, it is typically shorter. It is common to select a lifetime of between 1 and 24 hours (3600 to 86400 seconds).

## Encryption Algorithm

This is the algorithm used for encrypting the actual data that goes over the connection. See → *Advanced > Phase 1 > Encryption Algorithm* for more information.



If you are setting up your VPN gateway from scratch: The encryption algorithm for phase 2 can be different from the phase 1 encryption algorithm. For VPN gateways with severely limited encryption hardware, it may be appropriate to choose a less secure but better performing algorithm here, and set a more secure algorithm for phase 1.

## Authentication Algorithm

See → *Advanced > Phase 1 > Hash Algorithm*



Do not select "No authentication", unless you have a very special setup that does not support using authentication. **No authentication means exactly what it says and is extremely insecure.**

## Perfect Forward Secrecy (PFS)

Using Perfect Forward Secrecy provides additional security when encryption keys are re-negotiated. The setting must match what is configured on your VPN gateway.



If you are setting up your VPN gateway from scratch: Using Perfect Forward Secrecy is recommended.

If you are using a Cisco device with Easy VPN: Cisco devices can transmit their Perfect Forward Secrecy preference. Since using PFS is always more secure, VPN Tracker will use it when requested by a Cisco VPN gateway.

**VPN Gateway Setting:** Some devices do not have a dedicated setting for the PFS DH group. These devices typically use the same group as for phase 1.

## Establish a separate phase 2 tunnel for each remote network

When connecting to multiple remote networks, VPN Tracker can either establish a separate VPN tunnel (Security Association, SA) for each network, or send all traffic over a single tunnel. The single tunnel will use the first remote network as the endpoint.

Which setting to use depends on the VPN gateway. If you find that with a single tunnel you cannot access any remote network but the first, then try swapping the order of the remote networks. If you can now access the new first network, then you likely need this setting turned on (or, less likely, your VPN gateway supports only a single remote network for the connection).

Cisco EasyVPN-based VPN gateways are a special case, here you should almost always uncheck this setting **and** enable "Establish a Shared Tunnel to 0.0.0.0/0 for Split-Tunneling" in the Interoperability settings.

**Related Settings:** Basic > Network > Remote Networks  
Advanced > Interoperability > Cisco > Establish a Shared Tunnel to 0.0.0.0/0 for Split-Tunneling

**Availability:** The setting is available only if there are multiple remote networks, or when using an automatic configuration method that could lead to connecting to multiple remote networks.

## Certificates

### Send Certificate

If turned on, VPN Tracker will send the local certificate to the VPN gateway. This setting should normally be turned on. Only turn off this

setting if your VPN gateway has trouble dealing with certificates sent by connecting clients.

**Related Settings:** Basic > Authentication > Certificate

**Availability:** The setting is only available for certificate-based authentication.

### Send Request for Remote Certificate

If turned on, VPN Tracker will request the VPN gateway's certificate. This setting should normally be turned on. Only turn off this setting if your VPN gateway has trouble dealing with certificate requests from connecting clients. In that case, you'll need to have the VPN gateway's certificate in your keychain.

**Related Settings:** Basic > Authentication > Certificate

**Availability:** The setting is only available for certificate-based authentication.

### Verify Remote Certificate

This setting can be used to temporarily disable certificate verification for debugging purposes.



Do not turn off this option except for debugging purposes!

**Related Settings:** Basic > Authentication > Certificate

**Availability:** The setting is only available for certificate-based authentication.

## Traffic Control

Traffic Control provides more fine-grained control over the traffic that will be sent through the VPN or exempted from it.



Traffic Control is an advanced feature that can cause traffic not to be encrypted. If you are unsure whether Traffic Control can help with your particular scenario, please contact support.

### Always exempt the addresses below from the VPN

Use this setting to exempt certain addresses from the VPN that would otherwise be sent through it.

### Send only traffic for the addresses below over VPN

Use this setting to send only traffic for certain addresses through the VPN. This is useful for VPNs that require a Host to Everywhere topology if you only need to reach certain hosts over the VPN, but don't want all your Internet traffic to go through the VPN.



Traffic Control is limited by the VPN's topology and remote networks. It is not possible to send traffic over the VPN for addresses that are not part of the remote networks.

### Force traffic over the VPN if remote networks conflict with local networks

Private IP addresses are not globally unique. If your VPN connects to a "popular" network such as 192.168.1.0/24, it can easily happen that you find yourself connected to an 192.168.1.0/24 network locally as well. VPN Tracker will refuse to connect because there's no way to tell which traffic to send over the VPN, and which needs to reach the local network.

If you do not need any of the resources on the local network, VPN Tracker can try to connect anyway if you turn on this setting. VPN

Tracker will exempt critical local addresses (router, DNS, DHCP), but otherwise force all traffic for the remote network(s) over the VPN.

**Availability:** always

## NAT-Traversal

Set NAT-Traversal to "Automatic".

There are some very specific circumstances in which you may need to change the setting, please read and understand → *VPN and Network Address Translation (NAT)*, before making any changes to this setting.

**Availability:** always

## Connection Timeout

The default settings are more than sufficient for most setups. Only in extreme network environments with high packet loss or extremely high latency (think “connecting from a space probe back to earth”) will you have to increase the timeout (and/or the number of times VPN Tracker attempts to resend a packet).

**Availability:** always

## Interoperability

### Send INITIAL-CONTACT Message

For some devices it is necessary to send this message when establishing a VPN connection in order to tell the VPN gateway to clean up “old” VPN connections. However, other devices will disconnect all other VPN users upon receiving this message (in particular if multiple VPN users

connect from the same public IP address, or when users share an XAUTH account).

**Availability:** According to the selected device profile.

### Advertise as Dead Peer Detection Capable

VPN Tracker supports Dead Peer Detection (DPD) to detect if the other end of the connection is no longer responding. When this setting is turned on, VPN Tracker will tell the VPN gateway that it supports Dead Peer Detection.

For most VPN gateways (whether they support Dead Peer Detection or not) this option should be turned on. Only turn it off if you suspect that VPN Tracker offering to perform Dead Peer Detection causes a problem on the VPN gateway, or if the VPN gateway’s Dead Peer Detection implementation is broken.

**Related Settings:** Advanced > Interoperability > Perform active Dead Peer Detection

**Availability:** According to the selected device profile.

### Perform active Dead Peer Detection every ... seconds, if necessary

If the VPN gateway is Dead Peer Detection capable, but does not perform Dead Peer Detection itself, VPN Tracker can perform Dead Peer Detection.

For most VPN gateways (whether they support Dead Peer Detection or not) this option should be turned on. Only turn it off if you suspect that VPN Tracker performing Dead Peer Detection causes problems (such as unexpected disconnects because the VPN gateway is not responding but the VPN is working anyway).

**Related Settings:** Advanced > Interoperability > Advertise as Dead Peer Detection Capable

**Availability:** According to the selected device profile.

### Use ... as the Application Version during Mode Config

When performing Mode Config (or EasyVPN), VPN Tracker will identify itself as “VPN Tracker 365”. Identifying as a different client or version may be necessary to work with some VPN gateways.

To identify as a specific client, simply enter its name and version, e.g. “Cisco Systems VPN Client 4.8.0:Linux”.

**Related Settings:** Basic > Network Configuration

**Availability:** Available with a custom device profile or a Cisco device profile when using Mode Config or EasyVPN.

### Send Cisco Unity Vendor ID

This setting is necessary in order to use certain Cisco-specific extensions, such as EasyVPN. Turn on this setting if you are connecting to a Cisco device using a custom device profile (it is not necessary to use this setting when using one of the Cisco device profiles shipping with VPN Tracker).

**Availability:** Only available using a custom device profile. The setting is automatically used in all Cisco device profiles.

### Send Cisco Firewall Attribute during Mode Config

When checked, VPN Tracker will send a special attribute indicating the presence of a firewall. This may help to successfully connect to some Cisco devices.

**Related Settings:** Basic > Network Configuration

**Availability:** Only available with custom device profiles or Cisco device profiles when using EasyVPN (or Mode Config with the “Send Cisco Unity Vendor ID” option turned on).

### Establish a Shared Tunnel to 0.0.0.0/0 for Split-Tunneling

When checked, VPN Tracker will establish a single tunnel (Security Association, SA) to 0.0.0.0/0 and set suitable routes to achieve split-tunneling. This can noticeably speed up connecting to a Cisco VPN gateway with multiple remote networks using EasyVPN and resolve issues with idle timeouts for those connections.

This setting should be turned on when connecting to Cisco devices using Cisco EasyVPN.

**Related Settings:** Basic > Network Configuration

Advanced > Phase 2 > Establish a separate phase 2 tunnel for each remote network

**Availability:** Available when EasyVPN is used and “Establish a separate phase 2 tunnel for each remote network” is turned off.

## IPv6

### Prefer IPv6 VPN gateway address, if available

You will not normally need to change this setting. If your VPN gateway is reachable through IPv6 and its host name resolves to an IPv4 address as well as to an IPv6 address, VPN Tracker will use the IPv6 address if this setting is turned on.

**Related Settings:** Basic > VPN Gateway

**Availability:** According to the selected device profile.



## Additional Settings

**Additional Settings** ☒ Show additional settings

**Direct Link Detection** [MAC Address of Remote Network's Router](#) [Use Current Router](#)

**Credentials** Display credentials prompt for **30** seconds

☐ Always prompt for pre-shared key

☐ Always prompt for XAUTH credentials

☐ Use stored XAUTH password as passcode

**Proposal conflict resolution** **Use remote proposals if more secure**

**MTU** ☐ Set MTU for network used by VPN: **1280** bytes

**Padding** ☐ Randomize padding ☐ Randomize padding length up to **20** bytes

☒ Exclusive padding tail ☐ Strict padding check

**Nonce size** **16** bytes

**Delete Payloads** ☒ Treat delete payload in phase 2 as error

### Direct Link Detection

This setting helps VPN Tracker detect when your Mac is physically attached to the network you normally connect to through VPN so you can use VPN Shortcuts and the Network Scanner in those locations.

For example, if you use your MacBook at the office without VPN, and from home with VPN, you can teach VPN Tracker to recognize when you are connected to your office network and no VPN is needed.

To teach VPN Tracker to recognize a direct link to your remote network:

- ▶ Physically connect your Mac to the remote network of your VPN connection (e.g. if you connect to your office through VPN, connect your Mac to the office network). Direct link detection also works with wireless networks.
- ▶ Open VPN Tracker and go to Advanced > Additional Settings > Direct Link Detection
- ▶ Click “Use Current Router”

VPN Tracker will detect the local router’s unique hardware address (MAC address) and remember it. The next time you are connected to

this network and try to connect to the VPN, VPN Tracker will know that no VPN is needed.

You’ll also see a message in the log when Direct Link Detection is active:

```
13:44:16 Direct Link to Remote Network

Your computer is currently directly connected to the remote network. It is therefore not necessary (and not possible) to connect the VPN.

Please note: VPN Tracker detects if your computer is directly connected to the remote network through the Direct Link Detection setting. Should you have accidentally entered your current network there, simply remove it again to resolve the problem.
```

If you have a very complex network, you can teach VPN Tracker about more than one router. Simply click the green plus button to add more input fields.

**Related Settings:** Basic > Network > Remote Network(s)

**Availability:** always

### Display credentials prompt for ... seconds

When VPN Tracker asks for VPN connection passwords (pre-shared key, Extended Authentication (XAUTH) credentials), the password prompts are only displayed for a limited of time to indicate that most VPN gateways will drop the connection attempt if the password is not supplied within a short time.

If necessary, this setting lets you increase the time a password prompt is being displayed. This can be useful for accessibility purposes, or when dealing with devices that request the next passcode from a passcode generator token (which can take up to 1 minute).

Do not increase the timeout unless you have a specific reason to do so. Most devices will no longer expect a password after 15-60 seconds and thus the connection attempt will fail if entering a password takes too much time.

**Availability:** always

### Always prompt for the pre-shared key

### Always prompt for XAUTH credentials

If enabled VPN Tracker will always prompt for the pre-shared key and/or XAUTH password, even if one is stored in keychain.

If a pre-shared key or password is stored, the password entry field will be pre-filled with this password, but the “Store in Keychain” checkbox will be turned off in order to prevent you from accidentally replacing the stored password.

This settings is useful if

- ▶ You are using a VPN gateway that asks you to fill the password field with password/pin + a generated one-time passcode. In that case, you can store the password/pin in keychain and have it pre-filled, and then add the generated code every time you connect.
- ▶ You sometimes need to connect as a different XAUTH user but still want your “regular” XAUTH user account to be stored in keychain.

**Availability:** always

### Use stored XAUTH password as passcode

A VPN gateway can ask for an XAUTH password or for a generated one-time passcode. Since it does not make sense to store **one-time** passcodes in keychain, VPN Tracker does not offer this option by default.

However, some VPN gateways incorrectly ask for a passcode even though they actually expect a password. In that case, enable this option to permit storing the password in keychain etc.

**Availability:** always

### Proposal Conflict Resolution

When VPN Tracker and the VPN gateway disagree about the lifetime or the Perfect Forward Secrecy (PFS) setting, VPN Tracker can choose to

accept the VPN gateway’s proposal instead of insisting on its own settings (in which case the connection attempt would fail).

### Use remote proposals

VPN Tracker will use whatever settings the VPN gateway suggests, even if they are less secure

### Use remote proposals if more secure (strict)

VPN Tracker will use the settings the VPN gateway suggests if they are at least as secure as the current settings in VPN Tracker

### Use remote proposals if more secure

VPN Tracker will use the settings the VPN gateway suggests if they are at least as secure as the current settings in VPN Tracker. If the lifetime mismatches and the VPN gateway's lifetime is longer, VPN Tracker will attempt to use its own (shorter) lifetime. While this will allow initial connectivity, it may lead to the connection being dropped unexpectedly later on.

### Never use remote proposals

VPN Tracker will treat a mismatch as an error and stop connecting.

**Related Settings:** Advanced > Phase 2 > Lifetime  
Advanced > Phase 2 > Perfect Forward Secrecy (PFS)

**Availability:** Only available using a custom device profile.

### Manually set MTU for network used by VPN

VPN Tracker normally uses an MTU (maximum transfer unit) of 1280 bytes. In extremely rare circumstances it may be necessary to decrease the MTU further in order to avoid fragmentation of network packets.

If you have to decrease the MTU, please be aware that the MTU in VPN Tracker needs to be set to 52 bytes less than the actual MTU that can be used.



**Availability:** always

## Padding

These settings determine how VPN Tracker handles cryptographic padding. **You should not change these settings unless instructed to do so by technical support.**

**Availability:** Only available using a custom device profile.

## Nonce Size

Determines the size of the nonce for the Diffie-Hellman (DH) key exchange. **You should not change this setting unless instructed to do so by technical support.**

**Availability:** Only available using a custom device profile.

## Treat delete payloads in phase 2 as errors

A delete payload normally is a strong indication that the VPN gateway has terminated the connection, and the only recovery possible is a reconnect of the VPN. This setting disables this recovery mechanism and will cause dead connections for almost all users. **Do not uncheck this setting unless instructed to do so by technical support.**

**Availability:** Only available using a custom device profile.

## Actions Tab


The actions tab is explained in detail in → *Working with VPN Tracker*

## Export Tab

A description of the export settings can be found → *Exporting Connections*.

# VPN Tracker Preferences

## General Preferences



### Reconnect VPNs after quitting and re-opening

VPN Tracker can remember and reconnect the VPNs that were connected when you quit the application or restarted your Mac.

If you would like to temporarily disable automatic reconnect, hold down the option key while opening VPN Tracker.

### Open VPN Tracker at login

VPN Tracker can open automatically at login. By default, VPN Tracker will open hidden. If you would like VPN Tracker to be visible on login, uncheck the “Hide” checkbox in System Preferences > Users & Groups > Login Items.

To connect certain VPNs at launch, check the box on the Actions tab of the VPN(s) you would like to connect.

## Show VPN status in menu bar

VPN Tracker can show its status in the menu bar. For more information about what the menu bar item can do, see → *Menu Bar Item*


## Hide Dock Icon

Check this box if you want to control VPN Tracker entirely from the menu bar, with no application icon being displayed in the Dock.

## Automatically check for updates.

VPN Tracker can automatically check for updates so you never miss out on important improvements to VPN Tracker. When an update is available, you will be asked if you would like to download and install the update.

## Network Preferences



## Network Ports


VPN Tracker normally connects **from** network port 500, the default port for IPsec VPN, and port 4500 for NAT-Traversal (VPN Tracker always connects **to** ports 500, and 4500 on the VPN gateway end).

If VPN Tracker cannot connect **from** ports 500 and 4500 because they are already in use, it will resort to alternate ports if the setting is “Automatic”.

In case you need VPN Tracker to always use a specific port (and treat it as an error, should that port not be available), you may set specific network ports here.

## Test VPN availability of unknown Internet connections

VPN Tracker automatically tests if VPN is available over your current Internet connection before attempting to connect to your VPN. **Testing occurs only once for any given Internet connection** – for example, the first time you connect from a hotel’s Internet access, VPN Tracker will test the connection. When returning to that hotel a few months later, VPN Tracker usually won’t need to test again.



Testing your Internet connection enables VPN Tracker to adjust its NAT-Traversal settings depending on what the Internet connection supports. For more information about NAT-Traversal and how VPN Tracker is testing your Internet connection, see → *VPN and Network Address Translation (NAT)*

It is strongly recommended to let VPN Tracker test unknown Internet connections for their VPN availability: If VPN Tracker knows what NAT-Traversal mechanisms are supported by your current Internet connection, VPN Tracker will be able to avoid many common connectivity issues automatically.

However, if you are using VPN Tracker to secure access to internal networks from another internal network (e.g. securing a corporate Wi-Fi

network), it may be necessary to disable testing (entirely or just when connected to this particular network).

**To disable testing for all Internet connections (not recommended):**

- ▶ Open Preferences > Network
- ▶ Uncheck “Test VPN availability of unknown Internet connections”


**To disable testing for the current Internet connection:**

- ▶ Open the VPN Availability Test (Tools > VPN Availability Test)
- ▶ Click “More Details”
- ▶ Check “Ignore test result”

You can also choose to skip the test while the test is in progress.

To reset all skipped Internet connections and start testing again, click the button “Forget Skipped Locations” in Preferences > Network.

## Scanner Preferences



### Performance

This setting determines how aggressively VPN Tracker scans a network. On the slowest setting, VPN Tracker will only scan a single service on a single host at a time. On the fastest setting, many services and hosts will be scanned concurrently. This could trigger intrusion detection systems on the VPN gateway or other firewalls, and cause you to be blocked from network access.

A medium setting is recommended for good performance and low risk of being blocked.

### Timeout

By default, VPN Tracker waits for two seconds to receive a response from a service. Increase the timeout for slow (high latency) network connections or if hosts on the remote network are slow to respond.

Increasing the timeout significantly increases the time a scan will take to complete, but may also increase the accuracy of the results.


### Load website previews

VPN Tracker shows previews of websites that the Network Scanner has found. Loading these previews may require a significant amount of network bandwidth if there are many and/or complex websites.

You may want to disable website previews if you are being charged for network bandwidth, or if you are on a very low-bandwidth Internet connection.

## Notification Preferences

---



VPN Tracker can display notifications for events such as VPN connect and disconnect, status changes, or errors.

Use the “Notifications” popup to select those events that you would like to be notified about. You can customize the way notifications are displayed in System Preferences > Notifications.



# VPN Shortcuts Reference

This chapter describes the items available in VPN Shortcuts Collections and how to customize them to get the most out of VPN Shortcuts.

## Connecting to File Servers

To connect to a file server (network share), drag the “File Server” item to your VPN Shortcuts Collections. VPN Shortcuts must be in → *Edit Mode* to add items.

- ▶ Select the VPN that is required for accessing this file server (here, the VPN is called “London”).
- ▶ Select the type of server that you would like to connect to, and enter its IP address. There are several types of file servers that VPN Tracker can connect to.



If your VPN has a working → *Remote DNS* setup, you can use a host name instead of an IP address.

If there are file servers currently connected to your Mac, they will be shown in the list and you can select one of those directly.

When you’re done setting up the file server, leave the edit mode and click the item to test it.

You will be prompted for your username and password (if required), as well as for the volume(s) on the file server that you would like to access<sup>1</sup>.


<sup>1</sup> For NFS file servers, the share must be specified in the VPN Shortcuts file server item.



It is not possible to use Bonjour or NETBIOS names for accessing file servers. Please use IP addresses instead, or set up → *Remote DNS* to be able to use DNS host names.

## OS X File Servers (AFP)


Select “AFP Server” if your file server is a Mac running OS X, or an Apple Time Capsule. Some NAS (Network Attached Storage) devices can be accessed using AFP, please refer to your device’s documentation for details.



In addition to the server’s address, you may optionally enter the volume after the address, separated by a forward slash (“/”), e.g. 192.168.42.11/SharedDocs.

## Windows File Servers (SMB/CIFS)

Select “SMB/CIFS Server” if your file server is running Windows, or if you are connecting to a file server with Windows-compatible network shares. Many NAS devices offer SMB services.



In addition to the server’s address, you may optionally enter the share after the address, separated by a forward slash (“/”), e.g. 192.168.42.11/Documents.

## NFS Server


Select “NFS Server” if you are connecting to a file server running the Network File System (NFS). You must specify the entire path to the network share, e.g. 192.168.42.11/export/docs.

## WebDAV Server

Select “WebDAV Server” if you are connecting to a file server running the WebDAV protocol. WebDAV is a popular protocol for uploading files to web hosting.


## Opening Websites and other URLs

You can use the Web Browser item in VPN Shortcuts Collections to open a website.



The Web Browser item can open **any URL**, e.g. telnet://, ssh://, etc., so if you have an application that can open URLs, you can use it here.

When you're done setting up the item, leave the edit mode and click the item to test it.



URLs will open in the default application registered on the Mac for the URL. The icon will automatically change to reflect the application that will open. You can set a custom icon by clicking the gear icon in the upper right corner of the inspector.

## Accessing Windows PCs using Microsoft Remote Desktop

You can add Microsoft Remote Desktop connections as VPN Shortcut to share the screen of remote Windows PCs.




Microsoft Remote Desktop for Mac needs to be installed and a connection set up in order to use this feature. Microsoft Remote Desktop can be downloaded at <http://www.microsoft.com/mac>

To share the screen of a Windows PC, drag the “Microsoft Remote Desktop” item to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.



- ▶ Select the VPN that is required for accessing the Windows PC (here, the VPN is called “London”).
- ▶ Select the Microsoft Remote Desktop connection needed to connect to the Windows PC (here, the connection is called “BigBen”).



When you're done setting up the Microsoft Remote Desktop item, leave the edit mode and click the item to test it.



If you haven't set up a Microsoft Remote Desktop connection yet, you can do so right within the Microsoft Remote Desktop for Mac application. Any connections configured there can be selected in VPN Shortcuts.


## Accessing Windows PCs using CoRD

CoRD is an alternative to Microsoft Remote Desktop for Mac to share the screen of remote Windows PCs right from VPN Shortcuts Collections.




CoRD needs to be installed and a connection set up in order to use this feature. CoRD can be downloaded at <http://cord.sf.net>.

To share the screen of a Windows PC, drag the “CoRD” item to your VPN Shortcuts area. The VPN Shortcuts Collection must be in → *Edit Mode* to add items.



- ▶ Select the VPN that is required for accessing the Windows PC (here, the VPN is called “London”).
- ▶ Select the Microsoft Remote Desktop connection needed to connect to the Windows PC (here, the connection is called “Windows 8 Test”).



When you're done setting up the CoRD item, leave the edit mode and click the item to test it.


## Accessing your Macs using Screen Sharing (VNC)

All modern versions of OS X support Screen Sharing through VNC. Make sure Screen Sharing is enabled on the Mac whose screen you would like to share (System Preferences > Sharing).

To share the screen of a Mac, drag the “Screen Sharing” item to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.



- ▶ Select the VPN that is required for accessing the Mac (here, the VPN is called “London”).
- ▶ Enter the IP address of the Mac whose screen you would like to share. If your VPN has a working → *Remote DNS* setup, you can use a host name instead of an IP address.



When you're done setting up the Screen Sharing item, leave the edit mode and click the item to test it.

## Accessing your Macs using Apple Remote Desktop (ARD)

If you have Apple Remote Desktop (ARD) installed, you can use it to manage remote Macs over VPN right from a VPN Shortcuts Collection.




Apple Remote Desktop needs to be installed and the Mac needs to be in one of its computer lists in order to use this feature. More information about Apple Remote Desktop can be found at <http://www.apple.com/remotedesktop>

To observe or control a remote Mac, drag the “Apple Remote Desktop” item to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.



- ▶ Select the VPN that is required for accessing the Mac (here, the VPN is called “London”).
- ▶ Choose if you would like to control or observe the Mac.
- ▶ Enter the IP address of the Mac that you would like to manage. If your VPN has a working → *Remote DNS* setup, you can use a host name instead of an IP address.



When you're done setting up the Apple Remote Desktop item, leave the edit mode and click the item to test it.





The Apple Remote Desktop item will fall back to VNC Screen Sharing if the computer you're attempting to connect to is not in one of Apple Remote Desktop's computer lists.

## Accessing FileMaker Databases

If you have FileMaker installed, you can open remote (and local) databases and run scripts from VPN Shortcuts.




FileMaker needs to be installed to use this feature. Information about FileMaker can be found at <http://www.filemaker.com>

To open a FileMaker database, drag the “FileMaker” item to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.



- ▶ Select the VPN that is required for accessing the FileMaker server (here, the VPN is called “London”).
- ▶ Enter the IP address of the FileMaker server. If your VPN has a working → *Remote DNS* setup, you can use a host name instead of an IP address.
- ▶ Enter the name of the database.
- ▶ If you would like to run a script when opening the database, enter its name.




When you're done setting up the FileMaker item, leave the edit mode and click the item to test it.


## Opening Mac and Windows Applications

Use VPN Shortcuts to open any Mac application, as well as Windows applications from Virtual Machines running Windows.

To open any application, drag the “Custom App” icon to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.



- ▶ Select the VPN that you would like to connect prior to opening the app (here, the VPN is called “London”).
- ▶ Select the app to open (here: Numbers).
- ▶ Optionally, check the box to quit the app before the VPN is disconnected.



When you're done setting up the application item, leave the edit mode and click the item to test it.



The VPN settings determine which network traffic goes through the VPN. Putting an application on your VPN Shortcuts Collection will **not** cause its traffic to go through the VPN **unless** the associated VPN is configured to send that traffic through the VPN. More information can be found in → *Topology*.

## Windows Applications

To add Windows applications from your virtual machines, locate the folder that mirrors your VM's applications (e.g. Documents > Virtual Machines > Your Windows Machine > Applications) and choose the application from there.

You need a virtual machine software that makes Windows applications accessible through the OS X file system and the VM needs to be set up to share your Mac's network connection.

## Administrating OS X Server

You can manage OS X Server from a VPN Shortcuts Collection using the OS X Server app.



The OS X Server application needs to be installed on your Mac (OS X server itself does not have to be installed), and the server needs to be listed in the app to be accessible as a VPN Shortcut.

To add OS X Server, drag the "OS X Server" icon to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.



- ▶ Select the VPN that is required for accessing the server (here, the VPN is called "Office").
- ▶ Enter the IP address of the server. If your VPN has a working → *Remote DNS* setup, you can use a host name instead of an IP address.




## Automating Tasks Using AppleScript

You can use AppleScript to automate repetitive tasks that need a VPN: Uploading files to a server, getting the newest data from a database, sending files to a service for processing, etc.

To add an AppleScript, drag the “AppleScript” item to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.




- ▶ Select the VPN that you would like to connect prior to running the script (here, the VPN is called “London”).
- ▶ Enter the AppleScript. Use the Run and Compile buttons to test your script.




## Automating Tasks Using Automator

You can add Automator workflows to VPN Shortcuts Collection to automate repetitive tasks that require a VPN. Uploading files to a server, getting the newest data from a database, sending files to a service for processing, etc.

To add an Automator workflow, drag the “Automator” item to your VPN Shortcuts Collection. VPN Shortcuts must be in → *Edit Mode* to add items.



- ▶ Select the VPN that you would like to connect prior to running the Automator workflow (here, the VPN is called “London”).
- ▶ Drag the workflow into the inspector, or use the Select button to select a workflow from disk. Use the Run button to test your workflow.



If your script or workflow needs a file server to be connected, you can either connect the file server as part of the script, or use an → *Action* in your VPN to connect the file server.

# Accessing Files & Printers over VPN

## Using Finder to Connect to File Servers

### VPN Shortcuts or Finder? Your Choice!

VPN Shortcuts lets you connect to file servers right from within VPN Tracker (→ [Learn More](#)). However, if you wish, you can of course also use the Finder to connect to your file servers.


### To connect to your file server (network share):

- ▶ Switch to Finder by clicking its icon in the Dock
- ▶ Choose Go > Connect to Server from the menu bar on top of your screen. You can also use the keyboard shortcut ⌘-K




### If your file server is a Mac (AFP):

- ▶ Enter the IP address (e.g. 192.168.42.4)<sup>1</sup> of your server in the “Server Address” field and click “Connect”.



### If your file server is running Windows (SMB/CIFS):

- ▶ Enter “smb://” followed by the IP address (e.g. 192.168.42.14)<sup>1</sup> of your server and click “Connect”.



You will be prompted for your username and password (if required), as well as for the volume(s) on the file server that you would like to access. If your VPN has a working → *Remote DNS* setup, you can use a host name instead of an IP address.

### I don't know my file server's IP address. Can't I just access my file servers via the Finder Sidebar?

When using a VPN connection, your servers won't show up in the Finder sidebar because the network protocols used for this service, Bonjour and NETBIOS, do not travel over the VPN.

If you don't know your file server's IP address, you can easily find it out next time you're in your office network:


<sup>1</sup> If your VPN connection uses remote DNS, you can also use a DNS host name instead of an IP address.

## Printing over VPN

It is possible to print to network printers over VPN. The trick is to use the printers IP address (or DNS host name) when setting up the printer on your Mac. It is not possible to use printers that have been auto-detected by Bonjour over the VPN because your Mac does not know their IP address or DNS host name.

If you have a network printer that's already set up on your Mac, check if it is using Bonjour:



- ▶ Open System Preferences "Print & Fax".
- ▶ Click "Options & Supplies".
- ▶ If the URL starts with "mdns://" your printer is a Bonjour printer and you will need to add it again using its IP address.



## Adding a Network Printer for Printing Over VPN

Before starting, make sure you know your printer's IP address or DNS host name. To help your Mac auto-detect the printer settings, it is helpful if your Mac is physically connected to your remote network or connected to the VPN while you set up the printer.

- ▶ Open System Preferences "Print & Fax".
- ▶ Click the plus button to add a new printer.



- ▶ Select whether your printer is an IPP, LPD or HP JetDirect printer (your printer's administrator or its manual will be able to tell you which it is).
- ▶ Enter your printer's IP address.

- Wait until OS X has determined your printer type. This works only if the printer is reachable. If not, you'll have to select the printer driver yourself.
  - Click "Add" to add the new printer.
- 



In VPN Tracker Pro, you can add printers directly from the Network Scanner's results.

---

# L2TP / PPTP Connections PRO

Find out how to integrate OS X L2TP / PPTP connections into VPN Tracker.


OS X has a built-in VPN client that can connect to L2TP and PPTP VPNs. In VPN Tracker Pro, these connections are automatically integrated into the sidebar so you can use all your VPN connections from one place.

## Setting up a new L2TP or PPTP VPN in OS X


- ▶ Open System Preferences > Network.
- ▶ Click the '+' icon.
- ▶ Select the VPN interface and your type of VPN.
- ▶ Configure the VPN and click "Apply".

For further information, please click the question mark to open OS X Help.

The VPN will automatically appear in the sidebar in VPN Tracker under "Other VPN Connections" and can be controlled from there.



OS X L2TP/PPTP VPN connections are always associated with a specific network location. VPN Tracker therefore only shows those VPN connections that belong to the current network location (System Preferences > Network > Location).





# VPN and Network Address Translation (NAT)

VPN Tracker provides reliable VPN connectivity, even through routers that perform Network Address Translation (NAT). This chapter explains the technical background of Network Address Translation, the different NAT-Traversal methods available, and how VPN Tracker makes everything work seamlessly.

## Private IP Addresses

In the early years of the Internet, each computer had a worldwide unique IP address. When it became clear that the Internet was growing rapidly and would soon run out of IP addresses, certain blocks of IP addresses were reserved for use on private networks. These private IP addresses can be used over and over again in different private networks, they do not have to be unique worldwide.

The following IP address ranges are reserved for private use:

First IP Address	Last IP Address	Number of IP Addresses
192.168.0.0	192.168.255.255	65.536
10.0.0.0	10.255.255.255	16.777.216
172.16.0.0	172.31.255.255	1.048.576

## Network Address Translation (NAT)

When a computer with a private IP address accesses the Internet, it sends the request through its local router. The local router cannot simply forward the request to the Internet: The sender's private IP address is not unique outside its particular private network – in fact there can be millions of computers on the Internet worldwide that have the same private IP address at any given moment! Instead, it makes a few changes to the sender's information in the request:

- ▶ It replaces the private IP address of the sender with its own public IP address.
- ▶ If necessary, it changes the outgoing network port number so no other computer communicating with the recipient of the request uses the same network port (it also remembers which port was used by which computer on its private network).

It then forwards the request to the Internet.

When responses come back, the process needs to be reversed. Responses will come back on the same network port the request was sent out. The router can therefore easily look up which computer sent the original request.

- ▶ The router replaces the recipient of the response with the private IP address of the computer who sent the original request.
- ▶ If it had to change the network port, the router puts back the original network port.

It then forwards the response to its private network.

The entire process is called Network Address Translation (NAT). If you have a DSL or wireless router (e.g. an AirPort Base Station) at home, it is very likely performing Network Address Translation. In most offices, hotels, and Internet cafes you will be connecting to a private network that has a NAT router for accessing the Internet.



## NAT-Traversal

Network Address Translation used to be a problem for VPN connections: Once the VPN is established, the actual communication over the VPN uses a network protocol called ESP. Unlike the TCP and UDP network protocols you may be familiar with, ESP does not use network ports. Since NAT depends on being able to use network ports to identify the recipient of an incoming response, it cannot work with ESP out of the box. Two methods have been developed to deal with NAT-Traversal:

### IPSec Passthrough

For IPSec Passthrough, the local router needs to know about IPSec VPN and the ESP protocol. In its most basic form, the router simply sends all ESP traffic to the last host on its network that talked to the VPN gateway. Most NAT routers have some limitation on their IPSec Passthrough capability, for example it often cannot support more than a single computer connecting to the VPN.

Since the local router takes care of everything, no special support is required on the VPN gateway or the VPN client.

## NAT-Traversal

With NAT-Traversal, VPN Tracker wraps ESP into regular UDP packets (which have port numbers and can easily be handled by NAT routers). On the other end, the VPN gateway needs to remove the UDP “wrapper” before it can decrypt the VPN communication.

There are several versions of NAT Traversal. Some VPN gateways support only one form of NAT-Traversal, and some, particularly older or low-end VPN gateways, support none. **VPN Tracker and the VPN gateway automatically negotiate which form of NAT-Traversal, if any, to use.**


Since VPN Tracker and the VPN gateway take care of everything, no special support for NAT-Traversal is required from the local router,

though firewall rules or firmware issues could prevent NAT-Traversal from working.



If you are buying a new VPN gateway, make sure it supports all forms of NAT-Traversal – it is very likely that you will encounter Internet connections that require NAT-Traversal to work.


The following diagram shows how a VPN is established using different NAT-Traversal mechanisms:



## Testing for NAT-Traversal Support

As you can see from the diagram, there are a several points where the local router could interfere with the VPN. **VPN Tracker can detect such problems and in most cases work around them by selecting the most suitable NAT-Traversal method for any given situation – whether it's a hotel, an Internet cafe or your home Wi-Fi network.**

VPN Tracker runs a test the first time it encounters a new local router (that's the progress bar you see before the VPN connection is established).



Even though it may take a short moment, it's very important to run the test! It only needs to run a single time at any given location.

### What does the test do?

The test connects to a VPN gateway at equinix using all possible NAT-Traversal methods: IPsec Passthrough, NAT-Traversal (early drafts), and NAT-Traversal (RFC). VPN Tracker tests and remembers which methods worked, and from then on it will only use the working methods.

Should VPN Tracker ever encounter a situation where the local router blocks all VPN traffic, or where the properties of the local Internet connection would require a form of NAT-Traversal that is not supported by your VPN gateway, it will specifically tell you so.

### In what situations is the automatic test not sufficient?


The automatic test will work in almost all situations. It will help you to get hassle-free VPN connectivity at Internet cafes, hotels, airports – ba-

sically in all those places where you have little time and encounter routers that may not support all NAT-Traversal methods.

There is one specific situations in which the availability test may not give accurate results: If communication to your VPN gateway goes through a different router than Internet traffic, or is treated differently (firewall rules etc.).

Since the test VPN gateway is located on the Internet, the test results reflect the connectivity from your location to VPN gateways on the Internet, but may not be accurate for your VPN gateway if it is handled differently.

In that case, you can open the VPN Availability Test (Tools > Test VPN Availability) and tell VPN Tracker to ignore the test results for this specific location.



To disable testing entirely, go to → *VPN Tracker Preferences*.

### What if my local router changes? What if a firmware upgrade changes its capabilities?

If you exchange the router for a different device, VPN Tracker will notice automatically (it uses the router's hardware address (MAC) to remember which routers it already tested).

If only the firmware is updated, or you are using an Internet connection where NAT-Traversal happens off-site at your Internet Service Provider (ISP), VPN Tracker cannot detect a change automatically. In that case,

please open the VPN Availability Test (Tools > Test VPN Availability)  
and repeat the test.

# Certificates and Smart Cards

This chapter describes how VPN Tracker can be integrated into a PKI (Public Key Infrastructure) using digital certificates or smart cards.

## Getting Started

To use certificates with VPN Tracker, you will need certificates and a VPN gateway that can authenticate users through X.509 certificates (RSA signatures).

## Obtaining Certificates

**If you have an existing Public Key Infrastructure (PKI) that uses certificates:**

- ▶ Certificates (and private keys for the client/user certificates) need to be available in a format supported by the OS X keychain. If your users already have their certificates in their OS X keychain, there's nothing that needs to be done.

**If you have an existing Public Key Infrastructure (PKI) that uses smart cards:**

- ▶ Software is required to make your smart card certificates available in OS X through the keychain. If you have already installed your vendor's driver or software, you can easily determine if it satisfies this requirement by checking if your smart card appears as a keychain in the OS X Keychain Access application (Applications > Utilities > Keychain Access)
- ▶ If your vendor does not provide the necessary software, there may be a third party solution available

**If you do not have an existing Public Key Infrastructure (PKI) in place:**

- ▶ Use the Certificate Assistant built into the OS X Keychain Access application to create certificates (Keychain Access > Certificate Assistant). Some VPN gateways also can create and export certificates.

## VPN Gateway Prerequisites

- ▶ Your VPN gateway must support the use of authentication based on digital certificates (X.509 certificates)
- ▶ Configure your VPN gateway for certificate-based authentication. Refer to your vendor's documentation for details.

### What about Tokens?

We are using the term “smart card” to describe both an actual smart card that is placed into a card reader, and a USB token with a non-removable smart card chip that plugs directly into your Mac. From VPN Tracker's perspective, there is no difference if the smart card chip is accessed through a card reader, or built into a USB token.

There is also another type of token on the market: These tokens generate a one-time code (e.g. RSA SecurID). When using such tokens, the VPN gateway usually request the code through Extended Authentication (XAUTH). To use such tokens in VPN Tracker, simply set up your VPN gateway according to your vendor's instructions and enable XAUTH in VPN Tracker.

## Certificate Management in OS X

To use certificates with VPN Tracker, the certificates must be available in a keychain. This chapter therefore will first cover the basics of certificate management using the keychain on OS X, before showing how to include certificates in VPN Tracker.



In OS X, certificates (and their private keys) are stored in keychains. Keychains are managed using the Keychain Access application (found in Applications > Utilities).

A keychain protects the private key by only permitting access if the keychain has been unlocked using the appropriate password. Also, if applications attempt to access a private key in a keychain for the first time, the user is asked to permit access, even if the keychain is unlocked. By default, a user has a single keychain, the login keychain, protected with their password. It is possible to change the login keychain's password to a different one, and to create additional keychains.


## Importing Certificates

Certificates can be imported into a OS X keychain using any of the usual certificate formats (PEM, DER, PKCS#7, PKCS#12). To import a certificate, simply double-click the certificate file, or choose File > Import Items... in Keychain Access.

If the certificate contains a private key and the certificate file is protected by a password, you will be asked for this password:




If the certificate contained a private key, you will see both the certificate and its private key in the list after importing. A combination of a certificate and its private key is called an identity in OS X.



If only the public part of the certificate was imported, you will see only the certificate listed after importing.

## Importing Certificate Authorities

Importing a certificate authority works the same as importing a regular certificate. After importing, you will be asked if you want to trust this certificate authority. If you choose “Always Trust”, certificates signed by this certificate authority will be trusted automatically in the future.



## Checking a Certificate's Trust

Keychain Access easily lets you see if a given certificate is trusted, and if not, why not. Simply select the certificate and examine the top part of the Keychain Access window (if the details are not visible, choose View > Show Summary to display them):

### What Certificates Do I Need?

To use certificate-based authentication in VPN Tracker, you will need the following certificates in your OS X keychain:

### VPN Client:

- ▶ VPN client (VPN user) certificate **and**
- ▶ Private key belonging to the VPN client (VPN user) certificate

### VPN Gateway (optional):

- ▶ VPN gateway's certificate (without the private key) **or**
- ▶ Certificate authority (CA) that signed the VPN gateway's certificate. Its certificate must be set as trusted on your Mac. The VPN gateway must be capable of sending its actual certificate upon connection initiation, which is the case for almost all VPN gateways



You can easily check if a private key is available for a given certificate by selecting the “My Certificates” category in the left column in Keychain Access. If a certificate appears there, it has a private key available.

## Selecting Certificates in VPN Tracker

If you have not yet done so, set the authentication method to “Certificates”.

The screenshot shows the 'Network Configuration' section of the VPN Tracker interface. The 'Authentication' dropdown menu is open, showing three options: 'Pre-shared key' (checked), 'Certificates' (highlighted), and 'Hybrid Mode'. To the right of the dropdown, there are status messages: 'Pre-shared key not saved' and 'Username and password not saved'. Below the authentication section, the 'Identifiers' section shows fields for 'Local' and 'Remote' identifiers, both set to 'Fully Qualified Domain Name (FQDN)'.



Make sure your VPN gateway is already configured for certificate-based (X.509 certificates / RSA signatures) authentication before starting to configure VPN Tracker.

In the certificate selection window, select your certificate(s). The certificate selection window opens automatically if you are not yet using certificates. If you have already selected some certificates earlier, click the “Edit” button on the Basic tab.

The screenshot shows a dialog box titled 'Select the certificates for this connection'. It contains instructions for selecting local and remote certificates. The 'Local Certificate' dropdown is set to 'Please select an identity...'. The 'Remote Certificate' dropdown is set to '- Use certificate sent by VPN gateway -'. At the bottom, there are three buttons: 'Open Keychain Access...', 'Cancel', and 'OK'.


## Local Certificate

The local certificate is the certificate you are using to identify to the VPN gateway as a user/client. It is sometimes called client certificate or user certificate. A private key is required for the local certificate, since it must sign messages to the VPN gateway.

If you cannot find your certificate here even though you have imported it into the OS X keychain, make sure the corresponding private key is also available in the keychain. You can easily check that by selecting the “My Certificates” category in Keychain Access. If it does not appear there, the private key is missing.

### Inspecting a Certificate

Click the triangle to see the details for the selected certificate.



### Certificate

The remote certificate is the VPN gateway’s certificate. A private key is not needed. There are two options:

- ▶ Select your VPN gateway’s certificate **or**
- ▶ Select “Use certificate supplied by peer”<sup>1</sup> to use the certificate the VPN gateway sends upon connecting, and verify it against the certificate authorities installed on your Mac. If verification fails, you will be prompted to verify the certificate manually.

<sup>1</sup> Locked connections require the VPN gateway certificate or a trusted CA that signed the certificate. If your VPN gateway is not capable of transmitting its certificate, the certificate is always required.



Even though CA certificates may show up in the list, you should selecting a CA certificate as the remote certificate will not work.

### Certificates and Exported Connections

Certificates are never included in an exported connection, since most organizations with a PKI infrastructure already have well-established (and secure) procedures of distributing certificates to users in place. The exported connection **does include** the information **which certificates** were selected.

When exporting an unlocked connection:

- ▶ If the selected certificates are present on the recipient’s Mac, VPN Tracker will use these certificates
- ▶ If the selected certificated do not exist on the recipient’s Mac, the recipient will be able to select different certificates

When exporting a locked connection:

- ▶ The recipient will not be able to edit their VPN connection settings. It is therefore important to select the correct certificates before exporting

## Identifiers Based on Certificates

It is possible to use the information from certificates as an identifier for the VPN connection. To do this, set the Local (Remote) Identifier to Local (Remote) Certificate". VPN Tracker will then use the certificate’s information (such as subject, organization, country etc.) as the identifier for the connection.

### Certificate Identifier Types



## Advanced Certificate Settings

There are several settings on the Advanced tab that influence how certificates are verified. These options should usually be left enabled. For more information, see the → *Settings Reference*


## Using Smart Cards

Storing certificates on a smart card provides even more security than using certificate-based authentication with certificates stored locally on your Mac. This chapter shows how to set up smart card based authentication with VPN Tracker using Aladdin eToken.

## Vendor Software Installation

To access your smart card on your Mac, you will first have to install the software provided by your smart card vendor. The following steps show the software installation for Aladdin eToken.

### Step 1 – Start the installation




- ▶ The installation program will guide you through the necessary installation steps
- ▶ Make sure to carefully read all instructions

### Step 2 – Follow the installation wizard



### Step 3 – Finish the installation by logging out




- ▶ When the installation has finished, you will have to log out (and log back in) to complete the installation.



- ▶ The installation will provide you with two software applications. The **PKIMonitor** allows you to monitor the attached eToken devices, and the **eToken Properties** application lets you configure your eToken and import certificates onto the device.
- ▶ Please refer to your vendor's documentation for additional details on how to set up your smart card or token.

## Verifying Access

To verify that you are indeed able to access your smart card or token through the OS X keychain, start the Keychain Access application. You should be able to find your token in the keychain list on the left (use “View > Show Keychain List” if the keychain list is not displayed).



If you have not done so yet, import or create your certificates on the smart card now. The best way to do this is through the software tools provided by your smart card vendor (such as through the eToken Properties application when using Aladdin eToken). Make sure that the private key for your client/user certificate is also present on the smart card. You can easily verify this by selecting the “My Certificates” category in Keychain Access. If the certificate is displayed there, the private key is available.

## Selecting Smart Card Certificates in VPN Tracker

Selecting a certificate located on a smart card works exactly the same as selecting a regular certificate. Please refer to → *Selecting Certificates in VPN Tracker* for details.

## Troubleshooting Certificates

Most errors can be resolved quickly by carefully following the hints given by VPN Tracker in its log. However, here are some frequently asked questions that cannot be covered by the log hints.

### My connection works fine, but I am prompted for my keychain password or keychain access permission every time I connect

- ▶ If you are using a smart card, this behavior is inherent to the way smart cards work, storing the access code is not possible
- ▶ If you are using normal certificates stored in your keychain, please make sure the OS X keychain subsystem has write access to the keychain that your certificate and private key are stored in, and to the folder the keychain is in. You can run the **Keychain First Aid** tool that is part of Keychain Access (Keychain Access > Keychain First Aid) to verify permissions.

### My certificate is only in the Remote Certificate list, however, I want to select it as the Local Certificate


A certificate that is to be used as the local certificate must have its private key stored in the keychain (or on the smart card). If a certificate does not have a private key available, it will not be displayed in the Local Certificates list.

### I cannot add my certificate to the keychain: Keychain Access keeps complaining that the certificate already exists, but I searched for it and it is not there!

A certificate is uniquely identified by the combination of issuer (i.e. the certificate authority signing it), and the serial number. If your keychain already contains a certificate issued by the same certificate authority with the same serial number, it will not be possible to add another certificate with the same issuer and serial number combination, even though the rest of the certificate may be completely different.

Unfortunately, it is fairly easy to accidentally create certificates with duplicate serial numbers when using the OS X Certificate Assistant. There are two possible ways of resolving this problem:

- ▶ Recreate the certificate using an unused serial number (in Certificate Assistant, check the box “Let me override defaults” to modify the serial number)



- ▶ If you do not have the possibility to recreate the certificate, put the offending certificate into a separate keychain

### I followed the advice in the log and double-checked my configuration, but the connection still fails

Before contacting technical support, please run the Keychain First Aid tool that is part of Keychain Access (Keychain Access > Keychain First Aid). Then try connecting again. Also double-check that you have selected the correct certificates. A certificate authority (CA) certificate should never be selected as the local or remote certificate.

If the problem persists, and you need to contact us, please include the following information with your support request:

- ▶ A **Technical Support Report** from VPN Tracker (Help > Technical Support Report...)

- Screenshots of the VPN configuration on your VPN gateway, if possible
- The **output of the Terminal command** `security dump-keychain` (preferred), or **screenshots of the details of all certificates** used with the connection: In Keychain Access, select each certificate and choose “File > Get Info”. Make sure the details are visible (click the triangle, if necessary) and take a screenshot of the details.

# Choosing the Right VPN Device

## What You're Looking For

Whether you're shopping for a new device or are trying to find out if your existing router can act as a VPN gateway, these are the magic words you'll want to look for – if they're mentioned in the manual or data sheet, the device is probably suitable:

- ▶ IPsec VPN Access
- ▶ IPsec Tunnels
- ▶ <any number of> IPsec Tunnels
- ▶ <any number of> IPsec VPN connections
- ▶ <any number of> IPsec VPN users
- ▶ <any number of> IPsec SAs

### Misleading Feature Names

If a device lists *only* one or more of the following features, it probably cannot act as a VPN gateway:

- ▶ IPsec Passthrough
- ▶ VPN Passthrough
- ▶ IPsec NAT-Traversal

These features indicate that the device is capable of letting IPsec VPN connections pass through. They do not indicate whether the device is capable of offering VPN services itself.

### Other Types of VPNs

- ▶ L2TP or L2TP/IPsec
- ▶ PPTP

If your device offers only these types of VPNs, it may be possible to use the limited VPN client built-in to OS X. VPN Tracker lets you control these connections from inside VPN Tracker. Other VPN types, such as OpenVPN and proprietary SSL VPNs are not supported.

### Apple Airport Base Stations

AirPort base stations are only capable of passing through VPN connections, but do not provide VPN services (i.e. act as a VPN gateway) themselves. If you are using an AirPort base station, you will need to buy a dedicated VPN gateway to replace or work alongside your Airport base station.

## Recommended Devices

Now for the big question: Which device do we recommend?

Unfortunately there is no generic answer to this question. There are a lot of factors you'll need to consider, such as the number of VPN users you need to support, the type of Internet connection you have, etc.

Generally speaking, the most important features are

- ▶ Robust support for client-to-gateway connections (some older or low-end VPN gateways are designed to provide only a single gateway-to-gateway VPN that requires static IP addresses on both ends of the connection).
- ▶ Support for all forms of NAT-Traversal.
- ▶ Reasonable level of security (at least 3DES encryption, better AES, SHA-1 hash algorithms, better SHA-2, DH groups 2 and 5, better higher).
- ▶ If you expect more than one VPN user: Support for Extended Authentication (XAUTH) and a form of client provisioning (Mode Config, Cisco EasyVPN, SonicWALL DHCP over VPN, WatchGuard MobileUser VPN).

The technical support team at equinix has extensive experience with a large number of VPN gateways, so please feel free to email us with a brief outline of your requirements, and a list of devices you're considering, and we'll be happy to give you our take on them!

<http://vpntracker.com/support>

# Further Resources

## VPN Tracker

### VPN Tracker Interoperability Website

Up-to-date information about device compatibility and detailed configuration guides for many popular VPN gateway devices.

<http://vpntracker.com/interop>

### VPN Tracker Support Website

Large database of Frequently Asked Questions (FAQs), as well as downloads and the possibility to contact technical support.

<http://vpntracker.com/support>

### VPN Tracker Deployment Guide

Deployment resources and best practices.

<http://www.vpntracker.com/goto/vpntmanualdeployment>

## Computer Networking and VPNs

### The TCP/IP Guide

An book on networking and the most popular networking protocols. Also available for free to read online.

<http://www.tcpipguide.com>

### Wikipedia

- Internet Protocol (IP)  
[http://en.wikipedia.org/wiki/Internet\\_Protocol](http://en.wikipedia.org/wiki/Internet_Protocol)
- Subnets and Network Addressing:  
<http://en.wikipedia.org/wiki/Subnetwork>
- Private IP Addresses  
[http://en.wikipedia.org/wiki/Private\\_network](http://en.wikipedia.org/wiki/Private_network)

- Network Address Translation (NAT)  
[http://en.wikipedia.org/wiki/Network\\_address\\_translation](http://en.wikipedia.org/wiki/Network_address_translation)
- DNS  
[http://en.wikipedia.org/wiki/Domain\\_Name\\_System](http://en.wikipedia.org/wiki/Domain_Name_System)
- IPsec  
<http://en.wikipedia.org/wiki/IPsec>

# Keyboard Shortcuts

Action	Shortcut
<b>Managing connections</b>	
Start connection	⌘-Return
Reconnect	⌘-Option-Return
Edit VPN Shortcuts	⌘-Shift-E
New Connection	⌘-N
New VPN Shortcuts	⌘-Shift-N
New Group	⌘-Option-N <span>PRO</span>
Delete Connection or VPN Shortcuts	⌘-⌘
<b>Tools</b>	
Test VPN Availability	⌘-Option-W
Ping Host	⌘-Option-P
Lookup Host	⌘-Option-L
<b>Export &amp; Deployment</b>	
Import Connection	⌘-Shift-i
Export Connection	⌘-E <span>PRO</span>
Show Export Settings	⌘-Option-E <span>PRO</span>
<b>Window shortcuts</b>	
Open Log	⌘-L

Action	Shortcut
Show / Hide Main Window	⌘-0
Show / Hide Connection Details	⌘-i
Switch Tabs Status/Accounting/Scanner/Log	⌘-1 to ⌘-4
Switch Edit Tabs Basic/Advanced/Actions/Notes	⌘-Option-1 to 4
<b>Application shortcuts</b>	
Preferences	⌘-,
Hide VPN Tracker	⌘-H
Hide Others	⌘-Option-H
Close Window	⌘-W
Minimize Window	⌘-M
Quit VPN Tracker	⌘-Q